




Linux Professional Institute



# **Linux & LPIC Quick Reference Guide**

**3<sup>rd</sup> ed. 2015-07**

# Foreword

This guide stems from the notes I have been taking while working with Linux and preparing the LPIC-1 and LPIC-2 certifications. As such, it includes quite a good amount of topics for these exams, with some subjects handled in more details than others. I started writing this guide in 2013 and it is my aim to update and integrate it periodically.

This document is an independent publication and is not affiliated with, authorized by, sponsored by, or otherwise approved by the Linux Professional Institute. You can freely use and share this guide or the individual pages, both in electronic or in printed form, provided that you distribute it unmodified and not-for-profit. Please feel free to contact me for any error, inaccuracy, or unclear point so I can correct it in future editions.

Happy Linux hacking,

Daniele Raffo

## Suggested readings

- Adam Haeder et al., *LPI Linux Certification in a Nutshell*, O'Reilly
- Evi Nemeth et al., *UNIX and Linux System Administration Handbook*, O'Reilly
- Heinrich W. Klöpping et al., *The LPIC-2 Exam Prep*, <http://lpic2.unix.nl/>
- Mendel Cooper, *Advanced Bash-Scripting Guide*, <http://tldp.org/LDP/abs/html/>
- Colin Barschel, *Unix Toolbox*, <http://cb.vu/unixtoolbox.xhtml>
- <http://www.gnu.org/manual/>
- <http://www.commandlinefu.com/>
- Linux man pages

## Index

LVM.....	1	SQL.....	43	Routing.....	85
LVM commands.....	2	SQL SELECTs.....	44	iptables.....	86
System boot.....	3	SQL JOINs.....	45	NAT routing.....	87
SysV startup sequence.....	4	MySQL.....	46	SSH.....	88
Runlevels.....	5	MySQL status.....	47	SSH operations.....	89
SysV vs Systemd init scripts.....	6	MySQL tools.....	48	SSH configuration.....	90
/etc/inittab.....	7	X Window.....	49	GnuPG.....	91
Filesystem hierarchy.....	8	X Window tools.....	50	OpenVPN.....	92
Partitions.....	9	X11 keysim codes.....	51	Key bindings.....	93
Filesystem types.....	10	User accounts.....	52	udev.....	94
Swap.....	11	User management.....	53	Kernel.....	95
/etc/fstab.....	12	UID and GID.....	54	Kernel management.....	96
Filesystem operations.....	13	Privilege escalation.....	55	Kernel compile and patching.....	97
Filesystem maintenance.....	14	Terminals.....	56	Kernel modules.....	98
XFS, ReiserFS, CD-ROM fs.....	15	cron.....	57	/proc filesystem.....	99
AutoFS.....	16	at.....	58	System recovery.....	100
RAID.....	17	Localization.....	59	DNS.....	101
Bootloader.....	18	System time.....	60	DNS configuration.....	102
GRUB configuration.....	19	Syslog.....	61	DNS zone file.....	103
GRUB commands.....	20	E-mail.....	62	Apache.....	104
Package managers.....	21	SMTP.....	63	Apache configuration.....	105
Package management tools.....	22	Sendmail and Exim.....	64	Apache virtual hosts.....	106
Backup.....	23	Postfix.....	65	Apache directory protection.....	107
Command line.....	24	Postfix configuration.....	66	Apache SSL/TLS configuration.....	108
Text filters.....	25	Procmail.....	67	OpenSSL.....	109
File management.....	26	Courier POP configuration.....	68	CA.pl.....	110
I/O streams.....	27	Courier IMAP configuration.....	69	Samba.....	111
Processes.....	28	Dovecot login.....	70	Samba configuration.....	112
Signals.....	29	Dovecot mailboxes.....	71	Samba shares.....	113
vmstat.....	30	Dovecot POP and IMAP.....	72	Samba macros.....	114
Resource monitoring.....	31	Dovecot authentication.....	73	NFS.....	115
Regexp.....	32	FTP.....	74	/etc/exports.....	116
File permissions.....	33	CUPS.....	75	DHCP.....	117
File attributes.....	34	IP addressing.....	76	PAM.....	118
Links.....	35	Subnetting.....	77	LDAP.....	119
Find system files.....	36	Network services.....	78	OpenLDAP.....	120
Shell environment.....	37	Network configuration commands.....	79	SELinux.....	121
Scripting.....	38	Network tools.....	80	HTML components.....	122
Flow control.....	39	Network monitoring.....	81	HTML text.....	123
Text processors.....	40	Network system files.....	82	HTML images.....	124
Vi.....	41	Network configuration files.....	83	HTML tables and lists.....	125
Vi options.....	42	TCP Wrapper.....	84	7-bit ASCII table.....	126

Logical Volume Management (LVM) introduces an abstraction between physical and logical storage that permits a more versatile use of filesystems. LVM uses the Linux device mapper feature (`/dev/mapper`).

Disks, partitions, and RAID devices are made of Physical Volumes, which are grouped into a Volume Group. A Volume Group is divided into small fixed-size chunks called Physical Extents. Physical Extents are mapped one-to-one to Logical Extents. Logical Extents are grouped into Logical Volumes, on which filesystems are created.

### How to create a Logical Volume

- |  |   |
|--|---|
| 1. <code>pvcreate /dev/hda2 /dev/hdb5</code>             | Initialize the Physical Volumes to be used with LVM. Devices must be of partition type 0x8E (Linux LVM) |
| 2. <code>vgcreate -s 8M myvg0 /dev/hda2 /dev/hdb5</code> | Create a Volume Group and define the size of Physical Extents to 8 Mb (default value is 4 Mb)           |
| or <code>vgextend myvg0 /dev/hda2</code>                 | or add the Physical Volume to an existing Volume Group  |
| 3. <code>lvcreate -L 1024M -n mydata myvg0</code>        | Create a Logical Volume   |
| 4. <code>mkfs -t ext3 /dev/myvg0/mydata</code>           | Create a filesystem on the Logical Volume   |
| 5. <code>mount /dev/myvg0/mydata /mydata</code>          | The Logical Volume is now mounted and used  |

### How to increase the size of a Logical Volume (only if the underlying filesystem permits it)

- |   |  |
|---|--|
| 1. <code>vgextend myvg0 /dev/hdc</code>             | Extend the Volume Group using the space in hdc |
| 2. <code>lvextend -L 2048M /dev/myvg0/mydata</code> | Extend the Logical Volume                      |
| or <code>lvresize -L+2048M /dev/myvg0/mydata</code> |  |
| 3. <code>resize2fs /dev/myvg0/mydata</code>         | Extend the filesystem                          |

### How to reduce the size of a Logical Volume (only if the underlying filesystem permits it)

- |  |                           |
|--|---------------------------|
| 1. <code>resize2fs /dev/myvg0/mydata 900M</code>   | Shrink the filesystem     |
| 2. <code>lvreduce -L 900M /dev/myvg0/mydata</code> | Shrink the Logical Volume |
| or <code>lvresize -L-900M /dev/myvg0/mydata</code> |                           |

### How to snapshot and backup a Logical Volume

- |   |  |
|---|--|
| 1. <code>lvcreate -s -L 1024M -n snapshot0 /dev/myvg0/mydata</code> | Create the snapshot just like another Logical Volume |
| 2. <code>tar cvzf snapshot0.tar.gz snapshot0</code>                 | Backup the snapshot with any backup tool             |
| 3. <code>lvremove /dev/myvg0/snapshot0</code>                       | Delete the snapshot                                  |

<code>pvs</code>	Report information about Physical Volumes
<code>pvck</code>	Check Physical Volume metadata
<code>pvdisplay</code>	Display Physical Volume attributes
<code>pvscan</code>	Scan all disks for Physical Volumes
<code>pvremove</code>	Remove a Physical Volume
<code>pvmove</code>	Move the Logical Extents on a Physical Volume to wherever there are available Physical Extents (within the Volume Group) and then put the Physical Volume offline
<code>vgs</code>	Report information about Volume Groups
<code>vgck</code>	Check Volume Group metadata
<code>vgmerge</code>	Merge two Volume Groups
<code>vgimport</code>	Import a Volume Group into a system
<code>vgexport</code>	Export a Volume Group from a system
<code>vgchange</code>	Change Volume Group attributes
<code>vgextend</code>	Add a Physical Volume to a Volume Group
<code>vgreduce</code>	Remove a Physical Volume from a Volume Group
<code>lvs</code>	Report information about Logical Volumes
<code>lvchange</code>	Change Logical Volume attributes
<code>lvremove</code>	Remove a Logical Volume
<code>lvscan</code>	Scan all disks for Logical Volumes

Boot sequence	
<b>POST (Power-On Self Test)</b>	Low-level check of PC hardware.
<b>BIOS (Basic I/O System)</b>	Detection of disks and hardware.
<b>Chain loader GRUB (GRand Unified Bootloader)</b>	<p>GRUB stage 1 is loaded from the MBR and executes GRUB stage 2 from filesystem. GRUB chooses which OS to boot on. The chain loader hands over to the boot sector of the partition on which resides the OS.</p> <p>The chain loader also mounts <code>initrd</code>, an initial ramdisk (typically a compressed ext2 filesystem) to be used as the initial root device during kernel boot; this make possible to load kernel modules that recognize hard drives hardware and that are hence needed to mount the real root filesystem. Afterwards, the system runs <code>/linuxrc</code> with PID 1. (From Linux 2.6.13 onward, the system instead loads into memory <code>initramfs</code>, a cpio-compressed image, and unpacks it into an instance of <code>tmpfs</code> in RAM. The kernel then executes <code>/init</code> from within the image.)</p>
<b>Linux kernel</b>	<p>Kernel decompression into memory.</p> <p>Kernel execution.</p> <p>Detection of devices.</p> <p>The real root filesystem is mounted on <code>/</code> in place of the initial ramdisk.</p>
<b>init</b>	<p>Execution of <code>init</code>, the first process (PID 1). The system tries to execute in the following order:</p> <pre>/sbin/init /etc/init /bin/init /bin/sh</pre> <p>If none of these succeeds, the kernel will panic.</p>
<b>Startup</b>	The system loads startup scripts and runlevel scripts.
<b>X Server</b>	(Optional) The X Display Manager starts the X Server.

Some newer systems use UEFI (Unified Extensible Firmware Interface). UEFI does not use the MBR boot code; it has knowledge of partition table and filesystems, and stores its application files required for launch in a EFI System Partition, mostly formatted as FAT32.

After the POST, the system loads the UEFI firmware which initializes the hardware required for booting, then reads its Boot Manager data to determine which UEFI application to launch. The launched UEFI application may then launch another application, e.g. the kernel and `initramfs` in case of a boot loader like the GRUB.

OS startup sequence (SysV)	Debian	Red Hat
At startup <code>/sbin/init</code> executes all instructions on <code>/etc/inittab</code> . This script at first switches to the default runlevel...	<code>id:2:initdefault:</code>	<code>id:5:initdefault:</code>
... then it runs the following script (same for all runlevels) which configures peripheral hardware, applies kernel parameters, sets hostname, and provides disks initialization...	<code>/etc/init.d/rcS</code>	<code>/etc/rc.d/rc.sysinit</code> or <code>/etc/rc.sysinit</code>
... and then, for runlevel <i>N</i> , it calls the script <code>/etc/init.d/rc N</code> (i.e. with the runlevel number as parameter) which launches all services and daemons specified in the following startup directories:	<code>/etc/rcN.d/</code>	<code>/etc/rc.d/rcN.d/</code>
<p>The startup directories contain symlinks to the init scripts in <code>/etc/init.d/</code> which are executed in numerical order. Links starting with K are called with argument <code>stop</code>, links starting with S are called with argument <code>start</code>.</p> <pre>lrwxrwxrwx. 1 root root 14 Feb 11 22:32 K88sssd -&gt; ../init.d/sssd lrwxrwxrwx. 1 root root 15 Nov 28 14:50 K89rdisc -&gt; ../init.d/rdisc lrwxrwxrwx. 1 root root 17 Nov 28 15:01 S01sysstat -&gt; ../init.d/sysstat lrwxrwxrwx. 1 root root 18 Nov 28 14:54 S05cgconfig -&gt; ../init.d/cgconfig lrwxrwxrwx. 1 root root 16 Nov 28 14:52 S07iscsid -&gt; ../init.d/iscsid lrwxrwxrwx. 1 root root 18 Nov 28 14:42 S08iptables -&gt; ../init.d/iptables</pre> <p>The last script to be run is <code>S99local -&gt; ../init.d/rc.local</code>; therefore, an easy way to run a specific program upon boot is to call it from this script file.</p> <pre>/etc/init.d/boot.local /etc/init.d/before.local (SUSE) /etc/init.d/after.local (SUSE)</pre> <p>runs only at boot time, not when switching runlevel. runs only at boot time, before the scripts in the startup directories. runs only at boot time, after the scripts in the startup directories.</p>		
To add or remove services at boot sequence:	<code>update-rc.d service defaults</code> <code>update-rc.d -f service remove</code>	<code>chkconfig --add service</code> <code>chkconfig --del service</code>

Parameters (service operations) supported by the init scripts		
<code>start</code>	Start the service	Mandatory
<code>stop</code>	Stop the service	
<code>restart</code>	Restart the service (stop, then start)	
<code>status</code>	Display daemon PID and execution status	
<code>force-reload</code>	Reload configuration if the service supports this option, otherwise restart the service	
<code>condrestart</code> <code>try-restart</code>	Restart the service only if already running	Optional
<code>reload</code>	Reload service configuration	

Linux Standard Base (LSB)
<p>LSB defines a format to specify the default values on an init script <code>/etc/init.d/foo</code>:</p> <pre>### BEGIN INIT INFO # Provides: foo # Required-Start: bar # Default-Start: 2 3 4 5 # Default-Stop: 0 1 6 # Description: Service Foo init script ### END INIT INFO</pre> <p>Default runlevels and S/K symlinks values can also be specified as such:</p> <pre># chkconfig: 2345 85 15 # description: Foo service</pre>

Runlevel	Debian	Red Hat
<b>0</b>	Shutdown	
<b>1</b>	Single user / maintenance mode	
<b>2</b>	Multi-user mode (default)	Multi-user mode without network
<b>3</b>	Multi-user mode	Multi-user mode with network
<b>4</b>	Multi-user mode	Unused, for custom use
<b>5</b>	Multi-user mode	Multi-user mode with network and X (default)
<b>6</b>	Reboot	
<b>S</b>	Single user / maintenance mode (usually accessed through runlevel 1)	

The default runlevels are **2 3 4 5**

```
runlevel
who -r
```

Display the previous and the current runlevel

```
init runlevel
telinit runlevel
```

Change runlevel

```
init 0
telinit 0
shutdown -h now
halt
poweroff
```

Halt the system

```
init 6
telinit 6
shutdown -r now
reboot
```

Reboot the system

```
shutdown
```

Shut down the system in a secure way: all logged in users are notified via a message to their terminal, and login is disabled.  
This command can be run only by the root user and by those users (if any) listed in `/etc/shutdown.allow`

```
shutdown -h 16:00 message
shutdown -a
```

Schedule a shutdown for 4 PM and send a warning message to all logged in users

Non-root users that are listed in `/etc/shutdown.allow` can use this command to shut down the system

```
shutdown -f
shutdown -F
shutdown -c
```

Skip fsck on reboot

Force fsck on reboot

Cancel an already running shutdown

System V	Systemd	Action
<code>/etc/init.d/service operation</code> <code>service service operation</code> (Red Hat) <code>rcservice operation</code> (SUSE)	<code>systemctl operation service</code>	Perform one of these operations on the specified service: start stop restart status force-reload condrestart try-restart reload
<code>update-rc.d service defaults</code> (Debian) <code>chkconfig --add service</code> (Red Hat)		Add a service at boot
<code>update-rc.d -f service remove</code> (Debian) <code>chkconfig --del service</code> (Red Hat)		Remove a service at boot
When adding or removing a service at boot, startup directories will be updated by creating or deleting symlinks for the default runlevels: K symlinks for runlevels 0 1 6, and S symlinks for runlevels 2 3 4 5. In System V, the service will be run via the <code>xinetd</code> super server.		
<code>update-rc.d -f service \</code> <code>start 30 2 3 4 5 . stop 70 0 1 6 .</code>		Add a service on the default runlevels; create S30 symlinks for starting the service and K70 symlinks for stopping it
<code>chkconfig --levels 245 service on</code>		Add the service on runlevels 2 4 5
<code>chkconfig service on</code>	<code>systemctl enable service</code>	Add the service on default runlevels
<code>chkconfig service off</code>	<code>systemctl disable service</code>	Remove the service on default runlevels
<code>chkconfig service</code>	<code>systemctl is-enabled service</code>	Check if the service is enabled on the current runlevel
<code>chkconfig service reset</code>		Reset the on/off state of the service for all runlevels to whatever the Linux Standard Base specifies in the init script
<code>chkconfig service resetpriorities</code>		Reset the start/stop priorities of the service for all runlevels to whatever the Linux Standard Base specifies in the init script
<code>chkconfig --list service</code>		Display current configuration of service (its status and the runlevels in which it is active)
<code>chkconfig --list</code>	<code>systemctl list-unit-files \</code> <code>--type=service</code>	List all active services and their current configuration



/etc/inittab		
<pre># The default runlevel. id:2:initdefault:  # Boot-time system configuration/initialization script. # This is run first except when booting in emergency (-b) mode. si::sysinit:/etc/init.d/rcS  # What to do in single-user mode. ~~:S:wait:/sbin/sulogin  # /etc/init.d executes the S and K scripts upon change of runlevel. 10:0:wait:/etc/init.d/rc 0 11:1:wait:/etc/init.d/rc 1 12:2:wait:/etc/init.d/rc 2 13:3:wait:/etc/init.d/rc 3 14:4:wait:/etc/init.d/rc 4 15:5:wait:/etc/init.d/rc 5 16:6:wait:/etc/init.d/rc 6 # Normally not reached, but fall through in case of emergency. z6:6:respawn:/sbin/sulogin  # /sbin/getty invocations for the runlevels. # Id field must be the same as the last characters of the device (after "tty"). 1:2345:respawn:/sbin/getty 38400 tty1 2:23:respawn:/sbin/getty 38400 tty2</pre>		

/etc/inittab describes which processes are started at bootup and during normal operation; it is read and executed by `init` at bootup.

All its entries have the form **id:runlevels:action:process**

id	1-4 characters, uniquely identifies an entry. For gettys and other login processes it should be equal to the suffix of the corresponding tty	
runlevels	Runlevels for which the specified action must be performed. If empty, action is performed on all runlevels	
action	<div>respawn</div> <div>wait</div> <div>once</div> <div>boot</div> <div>bootwait</div> <div>off</div> <div>ondemand</div> <div>initdefault</div> <div>sysinit</div> <div>powerfail</div> <div>powerwait</div> <div>powerfailnow</div> <div>powerokwait</div> <div>ctrlaltdel</div> <div>kbdrequest</div> <div>Process will be restarted when it terminates</div> <div>Process is started at the specified runlevel and <code>init</code> will wait for its termination (i.e. execution of further lines of <code>/etc/inittab</code> stops until the process exits)</div> <div>Process is executed once at the specified runlevel</div> <div>Process is executed at system boot. Runlevels field is ignored</div> <div>Process is executed at system boot and <code>init</code> will wait for its termination. Runlevels field is ignored</div> <div>Does nothing</div> <div>Process is executed when an on-demand runlevel (A, B, C) is called</div> <div>Specifies the default runlevel to boot on. Process field is ignored</div> <div>Process is executed at system boot, before any <code>boot</code> or <code>bootwait</code> entries. Runlevels field is ignored</div> <div>Process is executed when power goes down and an UPS kicks in. <code>init</code> will not wait for its termination</div> <div>Process is executed when power goes down and an UPS kicks in. <code>init</code> will wait for its termination</div> <div>Process is executed when power is down and the UPS battery is almost empty</div> <div>Process is executed when power has been restored from UPS</div> <div>Process is executed when <code>init</code> receives a SIGINT via <b>CTRL</b> <b>ALT</b> <b>DEL</b></div> <div>Process is executed when a special key combination is pressed on console</div>	
process	Process to execute. If prepended by a <code>+</code> , <code>utmp</code> and <code>wtmp</code> accounting will not be done	

Filesystem Hierarchy Standard (FHS)	
/bin	Essential command binaries
/boot	Bootloader files (e.g. OS loader, kernel image, initrd)
/dev	Devices and partitions
/etc	System configuration files and scripts
/home	Home directories for users
/lib	Libraries for the binaries in /bin and /sbin, kernel modules
/lost+found	Storage directory for recovered files in this partition
/media	Mount points for removable media
/mnt	Mount points for temporary filesystems
/net	Access to directory tree on different external NFS servers
/opt	Optional, large add-on application software packages
/proc	Virtual filesystem providing kernel and processes information
/root	Home directory for the root user
/sbin	Essential system binaries, system administration commands
/srv	Data for services provided by the system
/tmp	Temporary files
/usr	User utilities and applications
/usr/bin	Non-essential command binaries (for all users)
/usr/lib	Libraries for the binaries in /usr/bin and /usr/sbin
/usr/sbin	Non-essential system binaries (daemons and services)
/usr/src	Source code
/usr/local	Software installed locally
/usr/local/bin	Local software binaries
/usr/local/games	Local game binaries
/usr/local/include	Local C header files
/usr/local/lib	Local libraries for the binaries in /usr/local/bin and /usr/local/sbin
/usr/local/man	Local manuals
/usr/local/sbin	Local system binaries
/usr/local/share	Local architecture-independent hierarchy
/usr/local/src	Local source code
/var	Variable files (e.g. logs, caches, mail spools)

<code>/dev/hda, /dev/hdb, /dev/hdc</code>	first, second, third IDE hard drive
<code>/dev/sda, /dev/sdb, /dev/sdc</code>	first, second, third SATA hard drive
<code>/dev/sda1, /dev/sda2, /dev/sda3</code>	first, second, third partition of the first SATA drive

#### Partitioning limits for Linux:

Max 4 primary partitions per hard disk, or 3 primary partitions + 1 extended partition

Partition numbers: 1-4

Max 11 logical partitions (inside the extended partition) per hard disk

Partition numbers: 5-15

The superblock contains information relative to the filesystem: e.g. filesystem type, size, status, metadata structures.

The Master Boot Record (MBR) is a 512-byte program located in the first sector of the hard disk; it contains information about hard disk partitions and has the duty of loading the OS.

Most modern filesystems use journaling; in a journaling filesystem, the journal logs changes before committing them to the filesystem, which ensures faster recovery and less corruption in case of a crash.

<code>fdisk /dev/sda</code>	Disk partitioning interactive tool
<code>sfdisk /dev/sda</code>	Disk partitioning non-interactive tool
<code>cfdisk</code>	Text-based UI fdisk
<code>gparted</code>	GUI fdisk
<code>fdisk -l /dev/sda</code>	List the partition table of <code>/dev/sda</code>
<code>partprobe</code>	After fdisk operations, this command can be run to notify the OS of partition table changes. Otherwise, these changes will take place only after reboot
<code>mkfs -t fstype device</code>	Create a filesystem of the specified type on a partition (i.e. format the partition). mkfs is a wrapper utility for the actual filesystem-specific maker commands:
<code>mkfs.ext2</code>	aka mke2fs
<code>mkfs.ext3</code>	aka mke3fs
<code>mkfs.ext4</code>	
<code>mkfs.msdos</code>	aka mkdosfs
<code>mkfs.reiserfs</code>	aka mkreiserfs
<code>mkfs.jfs</code>	
<code>mkfs.xfs</code>	
<code>mkfs -t ext2 /dev/sda</code>	Create a ext2 filesystem on <code>/dev/sda</code>
<code>mkfs.ext2 /dev/sda</code>	
<code>mke2fs /dev/sda</code>	
<code>mke2fs -j /dev/sda</code>	Create a ext3 filesystem (ext2 with journaling) on <code>/dev/sda</code>
<code>mkfs.ext3 /dev/sda</code>	
<code>mke3fs /dev/sda</code>	
<code>mkfs -t msdos /dev/sda</code>	Create a MS-DOS filesystem on <code>/dev/sda</code>
<code>mkfs.msdos /dev/sda</code>	
<code>mkdosfs /dev/sda</code>	
<code>mount</code>	Display the currently mounted filesystems.
<code>cat /proc/mounts</code>	The commands <code>mount</code> and <code>umount</code> maintain in <code>/etc/mtab</code> a database of currently mounted filesystems, but <code>/proc/mounts</code> is authoritative
<code>cat /etc/mtab</code>	
<code>mount -a</code>	Mount all devices listed in <code>/etc/fstab</code> (except those indicated as <code>noauto</code> )
<code>mount -t ext3 /dev/sda /foobar</code>	Mount a Linux-formatted disk. The mount point (directory) must exist
<code>mount -t msdos /dev/fd0 /mnt</code>	Mount a MS-DOS filesystem floppy disk to mount point <code>/mnt</code>
<code>mount /dev/fd0</code>	Mount a floppy disk. <code>/etc/fstab</code> must contain an entry for <code>/dev/fd0</code>
<code>umount /dev/fd0</code>	Unmount a floppy disk that was mounted on <code>/mnt</code> (device must not be busy)
<code>umount /mnt</code>	
<code>umount -l /dev/fd0</code>	Unmount the floppy disk as soon as it is not in use anymore
<code>mount -o remount,rw /</code>	Remount the root directory as read-write (supposing it was mounted read-only). Useful to change flags (in this case, read-only to read-write) for a mounted filesystem that cannot be unmounted at the moment
<code>mount -o nolock 10.7.7.7:/export/ /mnt/nfs</code>	Mount a NFS share without running NFS daemons. Useful during system recovery
<code>mount -t iso9660 -o ro,loop=/dev/loop0 cd.img /mnt/cdrom</code>	Mount a CD-ROM ISO9660 image file like a CD-ROM

Partition types		
0x00 Empty	0x4e QNX4.x 2nd part	0xa8 Darwin UFS
0x01 FAT12	0x4f QNX4.x 3rd part	0xa9 NetBSD
0x02 XENIX root	0x50 OnTrack DM	0xab Darwin boot
0x03 XENIX usr	0x51 OnTrack DM6 Aux1	0xaf HFS / HFS+
0x04 FAT16 <32M	0x52 CP/M	0xb7 BSDI fs
0x05 Extended	0x53 OnTrack DM6 Aux3	0xb8 BSDI swap
0x06 FAT16	0x54 OnTrackDM6	0xbb Boot Wizard hidden
0x07 HPFS/NTFS/exFAT	0x55 EZ-Drive	0xbe Solaris boot
0x08 AIX	0x56 Golden Bow	0xbf Solaris
0x09 AIX bootable	0x5c Priam Edisk	0xc1 DRDOS/sec (FAT-12)
0x0a OS/2 Boot Manager	0x61 SpeedStor	0xc4 DRDOS/sec (FAT-16 < 32M)
0x0b W95 FAT32	0x63 GNU HURD or SysV	0xc6 DRDOS/sec (FAT-16)
0x0c W95 FAT32 (LBA)	0x64 Novell Netware 286	0xc7 Syrinx
0x0e W95 FAT16 (LBA)	0x65 Novell Netware 386	0xda Non-FS data
0x0f W95 extended (LBA)	0x70 DiskSecure Multi-Boot	0xdb CP/M / CTOS / ...
0x10 OPUS	0x75 PC/IX	0xde Dell Utility
0x11 Hidden FAT12	0x80 Old Minix	0xdf BootIt
0x12 Compaq diagnostics	0x81 Minix / old Linux	0xe1 DOS access
0x14 Hidden FAT16 <32M	0x82 Linux swap / Solaris	0xe3 DOS R/O
0x16 Hidden FAT16	0x83 Linux	0xe4 SpeedStor
0x17 Hidden HPFS/NTFS	0x84 OS/2 hidden C: drive	0xeb BeOS fs
0x18 AST SmartSleep	0x85 Linux extended	0xee GPT
0x1b Hidden W95 FAT32	0x86 NTFS volume set	0xef EFI (FAT-12/16/32)
0x1c Hidden W95 FAT32 (LBA)	0x87 NTFS volume set	0xf0 Linux/PA-RISC boot
0x1e Hidden W95 FAT16 (LBA)	0x88 Linux plaintext	0xf1 SpeedStor
0x24 NEC DOS	0x8e Linux LVM	0xf4 SpeedStor
0x27 Hidden NTFS WinRE	0x93 Amoeba	0xf2 DOS secondary
0x39 Plan 9	0x94 Amoeba BBT	0xfb VMware VMFS
0x3c PartitionMagic recovery	0x9f BSD/OS	0xfc VMware VMKCORE
0x40 Venix 80286	0xa0 IBM Thinkpad hibernation	0xfd Linux raid autodetect
0x41 PPC PreP Boot	0xa5 FreeBSD	0xfe LANstep
0x42 SFS	0xa6 OpenBSD	0xff BBT
0x4d QNX4.x	0xa7 NeXTSTEP	

List of partition IDs and their names, as obtained by the command `sfdisk -T`

Most used Linux-supported filesystems	
Filesystem	Properties
ext2	Linux default filesystem, offering the best performances
ext3	ext2 with journaling
ext4	Linux journaling filesystem, upgrade from ext3
Reiserfs	Journaling filesystem
XFS	Journaling filesystem, developed by SGI
JFS	Journaling filesystem, developed by IBM
Btrfs	B-tree filesystem, developed by Oracle
msdos	DOS filesystem, supporting only 8-char filenames
umsdos	Extended DOS filesystem used by Linux, compatible with DOS
fat32	MS-Windows FAT filesystem
vfat	Extended DOS filesystem, with support for long filenames
ntfs	Replacement for fat32 and vfat filesystems
minix	Native filesystem of the MINIX OS
iso9660	CD-ROM filesystem
cramfs	Compressed RAM disk
nfs	Network filesystem, used to access files on remote machines
SMB	Server Message Block, used to mount Windows network shares
proc	Pseudo filesystem, used as an interface to kernel data structures
swap	Pseudo filesystem, Linux swap area

In Linux, the swap space is a virtual memory area (a file or a partition) used as RAM extension. Usually a partition is preferred because of better performances concerning fragmentation and disk speed. Although listed as filesystem type 0x82, the swap partition is not a filesystem but a raw addressable memory with no structure.

`fdisk`                      The `fdisk` tool can be used to create a swap partition

`dd if=/dev/zero of=/swapfile bs=1024 count=512000`              Create a 512-Mb swap file

`mkswap /swapfile`              Initialize a (already created) swap file or partition

`swapon /swapfile`              Enable a swap file or partition, thus telling the kernel that it can use it now

`swapoff /swapfile`              Disable a swap file or partition

`swapon -s`                      Any of these commands can be used to show the sizes of total and used swap areas  
`cat /proc/swaps`  
`cat /proc/meminfo`  
`free`  
`top`

/etc/fstab		Filesystems information			
# <filesystem>	<mount point>	<type>	<options>	<dump>	<pass>
/dev/sda2	/	ext2	defaults	0	1
/dev/sdb1	/home	ext2	defaults	1	2
/dev/cdrom	/media/cdrom	auto	ro,noauto,user,exec	0	0
/dev/fd0	/media/floppy	auto	rw,noauto,user,sync	0	0
proc	/proc	proc	defaults	0	0
/dev/hda1	swap	swap	pri=42	0	0
nfsserver:/dirs	/mnt	nfs	intr	0	0
//smbserver/jdoe	/shares/jdoe	cifs	auto,credentials=/etc/smbcreds	0	0
LABEL=/boot	/boot	ext2	defaults	0	0
UUID=652b786e-b87f-49d2-af23-8087ced0c667 /test ext4 errors=remount-ro,noatime 0 0					

filesystem	Device or partition. The filesystem can be identified either by its name, its label, or its UUID (Universal Unique Identifier) which is a 128-bit hash number that is associated to the partition at its initialization	
mount point	Directory on which the partition must be mounted	
type	Filesystem type, or <code>auto</code> if detected automatically	
options	defaults	Use the default options: <code>rw</code> , <code>suid</code> , <code>dev</code> , <code>exec</code> , <code>auto</code> , <code>nouser</code> , <code>async</code>
	ro	Mount read-only
	rw	Mount read-write
	suid	Permit SUID and SGID bit operations
	nosuid	Do not permit SUID and SGID bit operations
	dev	Interpret block special devices on the filesystem
	nodev	Do not interpret block special devices on the filesystem
	auto	Mount automatically at bootup, or when the command <code>mount -a</code> is given
	noauto	Mount only if explicitly demanded
	user	Partition can be mounted by any user
	nouser	Partition can be mounted only by the root user
	exec	Binaries contained on the partition can be executed
	noexec	Binaries contained on the partition cannot be executed
	sync	Write files immediately to the partition
	async	Buffer write operations and commit them later, or when device is unmounted
	rsi=nnn	NFS: Size for read transfers (from server to client)
	ws=nnn	NFS: Size for write transfers (from client to server)
	nfsvers=n	NFS: Version of NFS to use for transport
	retry=n	NFS: Time to keep retrying a mount attempt before giving up, in minutes
	timeo=n	NFS: Time after a mount attempt times out, in tenths of a second
options	intr	NFS: User can interrupt a mount attempt
	nointr	NFS: User cannot interrupt a mount attempt (default)
	hard	NFS: The system will try a mount indefinitely (default)
	soft	NFS: The system will try a mount until an RPC timeout occurs
	bg	NFS: The system will try a mount in the foreground, all retries occur in the background
	fg	NFS: All mount attempts occur in the foreground (default)
	tcp	NFS: Connect using TCP
	udp	NFS: Connect using UDP
dump	Dump (backup utility) options. 0 = do not backup	
pass	Fck (filesystem check utility) options. Defines in which order the filesystems should be checked; 0 = do not check	

<code>df</code>	Report filesystem disk space usage
<code>df -h</code>	Report filesystem disk space usage in human-readable output
<code>df /path/mydir</code>	Shows on which device the specified directory is mounted
<code>lsblk</code>	List information about all available block devices
<code>lsscsi</code>	List information about all SCSI devices
<code>blockdev --getbsz /dev/sda1</code>	Get the block size of the specified partition
<code>sync</code>	Flush the buffer and commit all pending writes. To improve performance of Linux filesystems, many write operations are buffered in RAM and written at once; writes are done in any case before unmount, reboot, or shutdown
<code>chroot /mnt/sysimage</code>	Start a shell with <code>/mnt/sysimage</code> as filesystem root. Useful during system recovery when the machine has been booted from a removable media (which hence is defined as the filesystem root)
<code>mknod /dev/sda</code>	Create a directory allocating the proper inode. Useful during system recovery when experiencing filesystem problems
<code>hdparm</code>	Get/set drive parameters for SATA/IDE devices
<code>hdparm -g /dev/hda</code>	Display drive geometry (cylinders, heads, sectors) of <code>/dev/hda</code>
<code>hdparm -i /dev/hda</code>	Display identification information for <code>/dev/hda</code>
<code>hdparm -tT /dev/hda</code>	Perform benchmarks on the <code>/dev/hda</code> drive
<code>hdparm -p 12 /dev/hda</code>	Reprogram IDE interface chipset of <code>/dev/hda</code> to mode 4. Use with caution!
<code>sdparm</code>	Access drive parameters for SCSI devices
<code>blkid -U 652b786e-b87f-49d2-af23-8087ced0c667</code>	Print the name of the specified partition, given its UUID
<code>blkid -L /boot</code>	Print the UUID of the specified partition, given its label
<code>findfs UUID=652b786e-b87f-49d2-af23-8087ced0c667</code>	Print the name of the specified partition, given its UUID
<code>findfs LABEL=/boot</code>	Print the name of the specified partition, given its label
<code>e2label /dev/sda1</code>	Print the label of the specified partition, given its name

`fsck device`

Check and repair a Linux filesystem (which must be unmounted). Corrupted files will be placed into the `/lost+found` of the partition. The exit code returned is the sum of the following conditions:

0	No errors	8	Operational error
1	File system errors corrected	16	Usage or syntax error
2	System should be rebooted	32	Fsck canceled by user
4	File system errors left uncorrected	128	Shared library error

`fsck` is a wrapper utility for the actual filesystem-specific checker commands:

```
fsck.ext2 aka e2fsck
fsck.ext3
fsck.ext4
fsck.msdos
fsck.vfat
fsck.cramfs
```

`fsck`  
`fsck -As`

Check and repair serially all filesystems listed in `/etc/fstab`

`fsck -f /dev/sda1`

Force a filesystem check on `/dev/sda1` even if it thinks is not necessary

`fsck -y /dev/sda1`

During filesystem repair, do not ask questions and assume that the answer is always yes

`fsck.ext2 -c /dev/sda1`  
`e2fsck -c /dev/sda1`

Check a ext2 filesystem, running the `badblocks` command to mark all bad blocks and add them to the bad block inode to prevent them from being allocated to files or directories

`tune2fs [options] device`

Adjust tunable filesystem parameters on ext2/ext3/ext4 filesystems

`tune2fs -j /dev/sda1`

Add a journal to this ext2 filesystem, making it a ext3

`tune2fs -C 4 /dev/sda1`

Set the mount count of the filesystem to 4

`tune2fs -c 20 /dev/sda1`

Set the filesystem to be checked by `fsck` after 20 mounts

`tune2fs -i 15d /dev/sda1`

Set the filesystem to be checked by `fsck` each 15 days

Both mount-count-dependent and time-dependent checking are enabled by default for all hard drives on Linux, to avoid the risk of filesystem corruption going unnoticed.

`dumpe2fs [options] device`

Dump ext2/ext3/ext4 filesystem information

`dumpe2fs -h /dev/sda1`

Display filesystem's superblock information (e.g. number of mounts, last checks, UUID)

`dumpe2fs /dev/sda1 | grep -i superblock`

Display locations of superblock (primary and backup) of filesystem

`dumpe2fs -b /dev/sda1`

Display blocks that are marked as bad in the filesystem

`debugfs device`

Interactive ext2/ext3/ext4 filesystem debugger

`debugfs -w /dev/sda1`

Debug `/dev/sda1` in read-write mode  
(by default, `debugfs` accesses the device in read-only mode)

Many hard drives feature the Self-Monitoring, Analysis and Reporting Technology (SMART) whose purpose is to monitor the reliability of the drive, predict drive failures, and carry out different types of drive self-tests.

The `smartd` daemon attempts to poll this information from all drives every 30 minutes, logging all data to `syslog`.

`smartctl -a /dev/sda`

Print SMART information for drive `/dev/sda`

`smartctl -s off /dev/sda`

Disable SMART monitoring and log collection for drive `/dev/sda`

`smartctl -t long /dev/sda`

Begin an extended SMART self-test on drive `/dev/sda`



```
xfs_growfs [options] mountpoint
```

Expand an XFS filesystem (there must be at least one spare new disk partition available)

```
xfs_info /dev/sda1
xfs_growfs -n /dev/sda1
```

Print XFS filesystem geometry

```
xfs_check [options] device
xfs_repair [options] device
```

Check XFS filesystem consistency

Repair a damaged or corrupt XFS filesystem

```
xfsdump -v silent -f /dev/tape /
```

Dump the root of a XFS filesystem to tape, with lowest level of verbosity. Incremental and resumed dumps are stored in the inventory database `/var/lib/xfsdump/inventory`

```
xfsrestore -f /dev/tape /
```

Restore a XFS filesystem from tape

```
xfsdump -J - / | xfsrestore -J - /new
```

Copy the contents of a XFS filesystem to another directory (without updating the inventory database)

```
reiserfstune [options] device
debugreiserfs device
```

Adjust tunable filesystem parameters on ReiserFS filesystem

Interactive ReiserFS filesystem debugger

```
mkisofs -r -o cdrom.img data/
```

Create a CD-ROM image from the contents of the target directory. Enable Rock Ridge extension and set all content on CD to be public readable (instead of inheriting the permissions from the original files)

CD-ROM filesystems	
Filesystem	Commands
ISO9660	<code>mkisofs</code> Create a ISO9660 filesystem
UDF (Universal Disk Format)	<code>mkudffs</code> Create a UDF filesystem
	<code>udffsck</code> Check a UDF filesystem
	<code>wrudf</code> Maintain a UDF filesystem
	<code>cdrwtool</code> Manage CD-RW drives (disk format, read/write speed, ...)
HFS (Hierarchical File System)	
CD-ROM filesystem extensions	
Rock Ridge	Contains the original file information (e.g. permissions, filename) for MS Windows 8.3 filenames
MS Joliet	Used to create more MS Windows friendly CD-ROMs
El Torito	Used to create bootable CD-ROMs

AutoFS permits automounting of filesystems, even for nonprivileged users.

AutoFS is composed of the `autofs` kernel module that monitors specific directories for attempts to access them, and in this case signals the `automount` userspace daemon which mounts the directory when it needs to be accessed and unmounts it when no longer accessed.

`/etc/auto.master`      Primary configuration file for AutoFS.  
Each line is an indirect map; each map file stores the configuration for the automounting of the subdir.

```
# mount point  map          options
/misc          /etc/auto.misc
/home          /etc/auto.home  --timeout=60
```

`/etc/auto.misc`      Configuration file for automounting of directory `/misc`.

```
# subdir  options                                filesystem
public    -ro,soft,intr                          ftp.example.org:/pub
cd         -fstype=iso9660,ro,nosuid,nodev        :/dev/cdrom
```

`/etc/auto.home`      Configuration file for automounting of directory `/home`.  
The `*` wildcard matches any subdir the system attempts to access, and the `&` variable takes the value of the match.

```
# subdir  options                                filesystem
*         -rw,soft,intr                          nfsserver.example.org:/home/&
```

The `/net/nfsserver/` tree allows nonprivileged users to automatically access any *nfsserver*.

RAID levels		
Level	Description	Storage capacity
RAID 0	Striping (data is written across all member disks). High I/O but no redundancy	Sum of the capacity of member disks
RAID 1	Mirroring (data is mirrored on all disks). High redundancy but high cost	Capacity of the smaller member disk
RAID 4	Parity on a single disk. I/O bottleneck unless coupled to write-back caching	Sum of the capacity of member disks, minus one
RAID 5	Parity distributed across all disks. Can sustain one disk crash	Sum of the capacity of member disks, minus one
RAID 6	Double parity distributed across all disks. Can sustain two disk crashes	Sum of the capacity of member disks, minus two
RAID 10 (1+0)	Striping + mirroring. High redundancy but high cost	Capacity of the smaller member disk
Linear RAID	Data written sequentially across all disks. No redundancy	Sum of the capacity of member disks

```
mdadm -C /dev/md0 -l 5 \
-n 3 /dev/sdb1 /dev/sdc1 /dev/sdd1 \
-x 1 /dev/sde1
```

Create a RAID 5 array from three partitions and a spare.  
Partitions type must be set to 0xFD.  
Once the RAID device has been created, it must be formatted e.g. via  
`mke2fs -j /dev/md0`

```
mdadm --manage /dev/md0 -f /dev/sdd1
mdadm --manage /dev/md0 -r /dev/sdd1
mdadm --manage /dev/md0 -a /dev/sdd1
```

Mark a drive as faulty, before removing it  
Remove a drive from the RAID array.  
The faulty drive can now be physically removed  
Add a drive to the RAID array.  
To be run after the faulty drive has been physically replaced

```
mdadm --misc -Q /dev/sdd1
mdadm --misc -D /dev/md0
mdadm --misc -o /dev/md0
mdadm --misc -w /dev/md0
```

Display information about a device  
Display detailed information about the RAID array  
Mark the RAID array as readonly  
Mark the RAID array as read & write

```
/etc/mdadm.conf
```

Configuration file for `mdadm`.

```
DEVICE /dev/sdb1 /dev/sdc1 /dev/sdd1 /dev/sde1
ARRAY /dev/md0 level=raid5 num-devices=3
        UUID=0098af43:812203fa:e665b421:002f5e42
        devices=/dev/sdb1,/dev/sdc1,/dev/sdd1,/dev/sde1
```

```
cat /proc/mdstat
```

Display information about RAID arrays and devices

Non-GRUB bootloaders										
LILO (Linux Loader)		Obsolete. Small bootloader that can be placed in the MBR or the boot sector of a partition. The configuration file is <code>/etc/lilo.conf</code> (run <code>/sbin/lilo</code> afterwards to validate changes).								
SYSLINUX	SYSLINUX	Able to boot from FAT and NTFS filesystems e.g. floppy disks and USB drives. Used for boot floppy disks, rescue floppy disks, and Live USBs.								
	ISOLINUX	<p>Able to boot from CD-ROM ISO 9660 filesystems. Used for Live CDs and bootable install CDs.</p> <p>The CD must contain the following files:</p> <table><tr><td><code>isolinux/isolinux.bin</code></td><td>ISOLINUX image, from the SYSLINUX distro</td></tr><tr><td><code>boot/isolinux/isolinux.cfg</code></td><td>ISOLINUX configuration</td></tr><tr><td><code>images/</code></td><td>Floppy images to boot</td></tr><tr><td><code>kernel/memdisk</code></td><td></td></tr></table> <p>The CD can be burnt with the command:</p> <pre>mkisofs -o output.iso -b isolinux/isolinux.bin -c isolinux/boot.cat \ -no-emul-boot -boot-load-size 4 -boot-info-table [CD root dir]</pre>	<code>isolinux/isolinux.bin</code>	ISOLINUX image, from the SYSLINUX distro	<code>boot/isolinux/isolinux.cfg</code>	ISOLINUX configuration	<code>images/</code>	Floppy images to boot	<code>kernel/memdisk</code>	
	<code>isolinux/isolinux.bin</code>	ISOLINUX image, from the SYSLINUX distro								
	<code>boot/isolinux/isolinux.cfg</code>	ISOLINUX configuration								
<code>images/</code>	Floppy images to boot									
<code>kernel/memdisk</code>										
PXELINUX	<p>Able to boot from PXE (Pre-boot eXecution Environment). PXE uses DHCP or BOOTP to enable basic networking, then uses TFTP to download a bootstrap program that loads and configures the kernel. Used for Linux installations from a central server or network boot of diskless workstations.</p> <p>The boot TFTP server must contain the following files:</p> <table><tr><td><code>/tftpboot/pxelinux.0</code></td><td>PXELINUX image, from the SYSLINUX distro</td></tr><tr><td><code>/tftpboot/pxelinux.cfg/</code></td><td>Directory containing a configuration file for each machine. A machine with Ethernet MAC address 88:99:AA:BB:CC:DD and IP address 192.0.2.91 (C000025B in hexadecimal) will search for its config filename in this order: 01-88-99-aa-bb-cc-dd C000025B C000025 C00002 C0000 C000 C00 C0 C default</td></tr></table>	<code>/tftpboot/pxelinux.0</code>	PXELINUX image, from the SYSLINUX distro	<code>/tftpboot/pxelinux.cfg/</code>	Directory containing a configuration file for each machine. A machine with Ethernet MAC address 88:99:AA:BB:CC:DD and IP address 192.0.2.91 (C000025B in hexadecimal) will search for its config filename in this order: 01-88-99-aa-bb-cc-dd C000025B C000025 C00002 C0000 C000 C00 C0 C default					
<code>/tftpboot/pxelinux.0</code>	PXELINUX image, from the SYSLINUX distro									
<code>/tftpboot/pxelinux.cfg/</code>	Directory containing a configuration file for each machine. A machine with Ethernet MAC address 88:99:AA:BB:CC:DD and IP address 192.0.2.91 (C000025B in hexadecimal) will search for its config filename in this order: 01-88-99-aa-bb-cc-dd C000025B C000025 C00002 C0000 C000 C00 C0 C default									
EXTLINUX	General-purpose bootloader like LILO or GRUB. Now merged with SYSLINUX.									

GRUB (Grand Unified Bootloader) is the standard boot manager on modern Linux distros, which may use either version: GRUB Legacy or GRUB 2.

GRUB Stage 1 (446 bytes), as well as the partition table (64 bytes) and the boot signature (2 bytes), is stored in the 512-byte MBR. It then accesses the GRUB configuration and commands available on the filesystem, usually on `/boot/grub`.

<code>/boot/grub/menu.lst</code> or <code>/boot/grub/grub.conf</code>		GRUB Legacy configuration file
<pre> timeout 10    # Boot the default kernel after 10 seconds default 0     # Default kernel is 0  # Section 0: Linux boot title  Debian      # Menu item to show on GRUB bootmenu root   (hd0,0)     # root filesystem is /dev/hda1 kernel /boot/vmlinuz-2.6.24-19-generic root=/dev/hda1 ro quiet splash initrd  /boot/initrd.img-2.6.24-19-generic  # Section 1: Windows boot title  Microsoft Windows XP root   (hd0,1)     # root filesystem is /dev/hda2 savedefault makeactive      # set the active flag on this partition chainloader +1  # read 1 sector from start of partition and run  # Section 2: Firmware/BIOS update from floppy disk title  Firmware update kernel /memdisk   # boot a floppy disk image initrd /floppy-img-7.7.7 </pre>		

Common kernel parameters:	<code>root=</code>	Specify the location of the filesystem root. This is a required parameter
	<code>ro</code>	Mount read-only on boot
	<code>quiet</code>	Disable non-critical kernel messages during boot
	<code>debug</code>	Enable kernel debugging
	<code>splash</code>	Show splash image
	<code>emergency</code>	Emergency mode: after the kernel is booted, run <code>sulogin</code> (single-user login) which asks for the root password for system maintenance, then run a Bash. Does not load <code>init</code> or any daemon or configuration setting.
	<code>init=/bin/bash</code>	Run a Bash shell (may also be any other executable) instead of <code>init</code>

<code>/boot/grub/grub.cfg</code>	GRUB 2 configuration file
<pre> # Linux Red Hat menuentry "Fedora 2.6.32" {    # Menu item to show on GRUB bootmenu set root=(hd0,1)             # root filesystem is /dev/hda1 linux /vmlinuz-2.6.32 ro root=/dev/hda5 mem=2048M initrd /initrd-2.6.32 }  # Linux Debian menuentry "Debian 2.6.36-experimental" { set root=(hd0,1) linux (hd0,1)/bzImage-2.6.36-experimental ro root=/dev/hda6 }  # Windows menuentry "Windows" { set root=(hd0,2) chainloader +1 } </pre>	

This file must not be edited manually. Instead, edit the files in `/etc/grub.d/` (these are scripts that will be run in order) and the file `/etc/default/grub` (the configuration file for menu display settings), then run `update-grub`.

The GRUB menu, presented at startup, permits to choose the OS or kernel to boot:

- ENTER** Boot the selected GRUB entry
- C** Get a GRUB command line
- E** Edit the selected GRUB entry (e.g. to edit kernel parameters in order to boot in single-user emergency mode, or to change IRQ or I/O port of a device driver compiled in the kernel)
- B** Boot the GRUB entry once it has been modified
- P** Bring up the GRUB password prompt (necessary if a GRUB password has been set)

```
grub-install /dev/sda      Install GRUB on first SATA drive
grub                      Access the GRUB shell
/boot/grub/device.map      This file can be created to map Linux device filenames to BIOS drives:

(fd0)  /dev/fd0
(hd0)  /dev/hda
```

GRUB Legacy shell commands			
<code>blocklist file</code>	Print the block list notation of a file	<code>kernel file</code>	Load a kernel
<code>boot</code>	Boot the loaded OS	<code>lock</code>	Lock a GRUB menu entry
<code>cat file</code>	Show the contents of a file	<code>makeactive</code>	Set active partition on root disk to GRUB's root device
<code>chainloader file</code>	Chainload another bootloader	<code>map drive1 drive2</code>	Map a drive to another drive
<code>cmp file1 file2</code>	Compare two files	<code>md5crypt</code>	Encrypt a password in MD5 format
<code>configfile file</code>	Load a configuration file	<code>module file</code>	Load a kernel module
<code>debug</code>	Toggle debugging mode	<code>modulenounzip file</code>	Load a kernel module without decompressing it
<code>displayapm</code>	Display APM BIOS information	<code>pause message</code>	Print a message and wait for a key press
<code>displaymem</code>	Display memory configuration	<code>quit</code>	Quit the GRUB shell
<code>embed stage device</code>	Embed Stage 1.5 in the device	<code>reboot</code>	Reboot the system
<code>find file</code>	Find a file	<code>read address</code>	Read a 32-bit value from memory and print it
<code>fstest</code>	Toggle filesystem test mode	<code>root device</code>	Set the current root device
<code>geometry drive</code>	Print information on a drive geometry	<code>rootnoverify device</code>	Set the current root device without mounting it
<code>halt</code>	Shut down the system	<code>savedefault</code>	Save current menu entry as the default entry
<code>help command</code>	Show help for a command, or the available commands	<code>setup device</code>	Install GRUB automatically on the device
<code>impsprobe</code>	Probe the Intel Multiprocessor Specification	<code>testload file</code>	Test the filesystem code on a file
<code>initrd file</code>	Load an initial ramdisk image file	<code>testvbe mode</code>	Test a VESA BIOS EXTENSION mode
<code>install options</code>	Install GRUB (deprecated, use <code>setup</code> instead)	<code>uppermem kbytes</code>	Set the upper memory size (only for old machines)
<code>ioprobe drive</code>	Probe I/O ports used for a drive	<code>vbeprobe mode</code>	Probe a VESA BIOS EXTENSION mode

Low-level package managers	Debian	Red Hat
Install a package file	<code>dpkg -i package.deb</code>	<code>rpm -i package.rpm</code> <code>rpm -i ftp://host/package.rpm</code> <code>rpm -i http://host/package.rpm</code>
Remove a package	<code>dpkg -r package</code>	<code>rpm -e package</code>
Upgrade a package (and remove old versions)		<code>rpm -U package.rpm</code>
Upgrade a package (only if an old version is already installed)		<code>rpm -F package.rpm</code>
List installed packages and their state	<code>dpkg -l</code>	<code>rpm -qa</code>
List the content of an installed package	<code>dpkg -L package</code>	<code>rpm -ql package</code>
List the content of a package file	<code>dpkg -c package.deb</code>	<code>rpm -qpl package.rpm</code>
Show the package containing a specific file	<code>dpkg -S file</code>	<code>rpm -qf file</code>
Verify an installed package		<code>rpm -V package</code>
Reconfigure a package	<code>dpkg-reconfigure package</code>	
Install a package source file		<code>rpm -i package.src.rpm</code>
Compile a package source file		<code>rpm -ba package.spec</code>
High-level package managers		
Install a package	<code>apt-get install package</code>	<code>yum install package</code>
Install a package file		<code>yum install package.rpm</code> <code>yum localinstall package.rpm</code>
Remove a package	<code>apt-get remove package</code>	<code>yum remove package</code>
Upgrade an installed package		<code>yum update package</code>
Upgrade all installed packages	<code>apt-get upgrade</code>	<code>yum update</code>
Upgrade all installed packages and handle dependencies with new versions	<code>apt-get dist-upgrade</code>	
Get the source code for a package	<code>apt-get source package</code>	
Check for broken dependencies and update package cache	<code>apt-get check</code>	
Fix broken dependencies	<code>apt-get install -f</code>	
Update information on available packages	<code>apt-get update</code>	
List all available packages		<code>yum list</code>
Search for a package	<code>apt-cache search package</code>	<code>yum search package</code>
Show package dependencies	<code>apt-cache depends package</code>	<code>yum deplist package</code>
Show package records	<code>apt-cache show package</code>	<code>yum list package</code>
Show information about a package	<code>apt-cache showpkg package</code>	<code>yum info package</code>
Update information about package contents	<code>apt-file update</code>	
List the content of an uninstalled package	<code>apt-file list package</code>	
Show the package containing a specific file	<code>apt-file search file</code>	<code>yum whatprovides file</code>
Add a CD-ROM to the sources list	<code>apt-cdrom add</code>	
Download package and resolve dependencies		<code>yumdownloader --resolve package</code>
Show URLs that would be downloaded		<code>yumdownloader --urls package</code>
Print list of available repositories	<code>cat /etc/apt/sources.list</code>	<code>yum repolist</code> <code>cat /etc/yum.repos.d/*.repo</code>
Package format	compressed with <code>ar</code>	compressed with <code>cpio</code>

High-level package managers are able to install remote packages and automatically solve dependencies.

Text-based UI or graphical tools	Debian	Red Hat
Manage packages and dependencies	aptitude	pirut
	dselect	
	synaptic	
Other tools		
Convert a RPM package to DEB and install it. Might break the package system!	alien -i package.rpm	
Convert a RPM package to cpio archive		rpm2cpio package.rpm



```
dd if=/dev/sda of=/dev/sdb
dd if=/dev/sda1 of=sda1.img
dd if=/dev/cdrom of=cdrom.iso bs=2048
rsync -rzv /home /tmp/bak
rsync -rzv /home/ /tmp/bak/home
```

```
rsync -avz /home root@10.0.0.7:/backup/
```

Copy the content of one hard disk over another, byte by byte

Create the image of a partition

Create an ISO file from a CD-ROM, using a block size of 2 Kb

Synchronize the content of the home directory with the temporary backup directory. Use recursion, compression, and verbosity. For all transfers subsequent to the first, rsync only copies the blocks that have changed, making it a very efficient backup solution in terms of speed and bandwidth

Synchronize the content of the home directory with the backup directory on the remote server, using SSH. Use archive mode (operates recursively and preserves owner, group, permissions, timestamps, and symlinks)

### Archive formats

ls   cpio -o > myarchive.cpio ls   cpio -oF myarchive.cpio	Create a cpio archive of all files that are on the current directory
find /home/   cpio -o > homedirs.cpio	Create a cpio archive of all users' home directories
cpio -id < myarchive.cpio	Extract all files from a cpio archive, recreating the directory structure
cpio -i -t < myarchive.cpio	List the contents of a cpio archive file without extracting it
gzip myfile	Compress a file with gzip
gunzip myfile.gz	Decompress a gzip-compressed file
gunzip -tv myfile.gz	Test the integrity of a gzip-compressed file
zcat myfile.gz	Read a gzip-compressed text file
bzip2 myfile	Compress a file with bzip2
bunzip2 myfile.bz2	Decompress a bzip2-compressed file
bzcat myfile.bz2	Read a bzip2-compressed text file
tar cvf myarc.tar mydir/	Create a tarred archive
tar cvzf myarc.tar.gz mydir/	Create a tarred gzip-compressed archive
tar xvzf myarc.tar.gz	Extract a tarred gzip-compressed archive
tar cvjf myarc.tar.bz2 mydir/	Create a tarred bzip2-compressed archive
tar xvjf myarc.tar.bz2	Extract a tarred bzip2-compressed archive
tar cvJf myarc.tar.xz mydir/	Create a tarred xz-compressed archive
tar xvJf myarc.tar.xz	Extract a tarred xz-compressed archive
tar tvf myarc.tar	List the contents of the tarred archive without extracting it
rar a myarc.rar mydir/	Create a RAR archive
unrar x myarc.rar	Extract a RAR archive

### Tape libraries

Devices	/dev/st0	First SCSI tape device
	/dev/nst0	First SCSI tape device (no-rewind device file)
Utility for magnetic tapes	mt -f /dev/nst0 asf 3	Position the tape at the start of 3 <sup>rd</sup> file
Utility for tape libraries	mtx -f /dev/sg1 status	Display status of tape library
	mtx -f /dev/sg1 load 3	Load tape from slot 3 to drive 0
	mtx -f /dev/sg1 unload	Unload tape from drive 0 to original slot
	mtx -f /dev/sg1 transfer 3 4	Transfer tape from slot 3 to slot 4
	mtx -f /dev/sg1 inventory	Force robot to rescan all slots and drives
	mtx -f /dev/sg1 inquiry	Inquiry about SCSI media device (Medium Changer = tape library)

<code>man <i>command</i></code>	Show the man page for a command
<code>man 7 <i>command</i></code>	Show section 7 of the command man page
<code>man man</code>	<p>Show information about man pages' sections:</p> <ol style="list-style-type: none"> <li>1 Executable programs or shell commands</li> <li>2 System calls (functions provided by the kernel)</li> <li>3 Library calls (functions within program libraries)</li> <li>4 Special files</li> <li>5 File formats and conventions</li> <li>6 Games</li> <li>7 Miscellaneous</li> <li>8 System administration commands (usually only for root)</li> <li>9 Kernel routines</li> </ol>
<code>cd <i>directory</i></code>	Change to the specified directory
<code>cd -</code>	Change to the previously used directory
<code>pwd</code>	Print the current working directory
<code>pushd <i>directory</i></code>	Adds the directory to the top of the directory stack, making it the new current working directory
<code>popd</code>	Removes the top directory from the directory stack and changes to the new top directory
<code>history</code>	<p>Show the history of command lines executed up to this moment.  Commands prepended by a space will be executed but will not show up in the history.  After the user logs out from Bash, history is saved into <code>~/.bash_history</code></p>
<code>!<i>n</i></code>	Execute command number <i>n</i> in the command line history
<code>history -c</code>	Delete command line history
<code>watch <i>command</i></code>	Execute <i>command</i> every 2 seconds
<code>watch -d -n 1 <i>command</i></code>	Execute <i>command</i> every second, highlighting the differences in the output
<code>cat /etc/debian_version</code> (Debian) <code>cat /etc/fedora-release</code> (Fedora) <code>cat /etc/redhat-release</code> (Red Hat)	Print the version of the Linux distribution
<code>vlock</code> <code>away</code>	Lock the virtual console (terminal)

Almost all Linux commands accept the option `-v` (verbose), and many commands also accept the option `-vv` (very verbose).

Bash directory shortcuts	
<code>.</code>	Current directory
<code>..</code>	Parent directory
<code>~</code>	Home directory of current user
<code>~jdoe</code>	Home directory of user jdoe
<code>~-</code>	Previously used directory

<code>cat myfile</code>	Print a text file
<code>cat myfile1 myfile2 &gt; myfile3</code>	Concatenate text files
<code>cat &gt; myfile &lt;&lt;EOF</code> <i>line 1</i> <i>line 2</i> <i>line 3</i> EOF	Creates a Here Document, storing the lines entered in input to a file
<code>head myfile</code> <code>head -n 10 myfile</code>	Print the first 10 lines of a text file
<code>tail myfile</code> <code>tail -n 10 myfile</code>	Print the last 10 lines of a text file
<code>tail -f myfile</code>	Output appended data as the text file grows; useful to read logs in realtime
<code>tac myfile</code>	Print a text file in reverse, from last line to first line
<code>fmt -w 75 myfile</code>	Format a text file so that each line has a max width of 75 chars
<code>pr myfile</code>	Format a text file for a printer
<code>nl myfile</code>	Prepend line numbers to a text file
<code>wc myfile</code>	Print the number of lines, words, and bytes of a text file
<code>join myfile1 myfile2</code>	Join lines of two text files on a common field
<code>paste myfile1 myfile2</code>	Merge lines of text files
<code>split -l 1 myfile</code>	Split a text file into 1-line files (named <code>xaa</code> , <code>xab</code> , <code>xac</code> , and so on)
<code>uniq myfile</code>	Print the unique lines of a text file, omitting consecutive identical lines
<code>sort myfile</code>	Sort alphabetically the lines of a text file
<code>expand myfile</code>	Convert tabs into spaces
<code>unexpand myfile</code>	Convert spaces into tabs
<code>od myfile</code>	Dump a file into octal
<code>grep foo myfile</code>	Print the lines of a file containing foo
<code>grep -v foo myfile</code>	Print the lines of a file not containing foo
<code>grep -v -e foo -e bar myfile</code>	Print the lines of a file not containing neither foo nor bar
<code>cut -d: -f3 myfile</code>	Cut the lines of a file, considering <code>:</code> as the delimiter and printing only the 3 <sup>rd</sup> field
<code>cut -d: -f1 /etc/passwd</code>	Print the list of user accounts in the system
<code>cut -c3-50 myfile</code>	Print character 3 to 50 of each line of a file
<code>sed s/foo/bar/ myfile</code>	Stream Editor: Replace the first occurrence of foo with bar
<code>sed s/foo/bar/g myfile</code>	Replace all occurrences of foo with bar
<code>sed -n '7,13p' myfile</code>	Print line 7 to 13 of a text file
<code>tr a-z A-Z &lt;myfile</code> <code>tr [:lower:] [:upper:] &lt;myfile</code>	Translate characters: Convert all lowercase into uppercase in a text file
<code>tr -d 0-9 &lt;myfile</code> <code>tr -d [:digit:] &lt;myfile</code>	Delete all digits from a text file
<code>zcat</code>	Print a gzipped file on stdout
<code>zgrep</code>	<code>grep</code> search in a gzipped file
<code>zless</code>	<code>less</code> for gzipped files
<code>zmore</code>	<code>more</code> for gzipped files

<code>cp myfile myfile2</code>	Copy a file
<code>cp myfile mydir/</code>	Copy a file to a directory
<code>mv myfile myfile2</code>	Rename a file
<code>mv myfile mydir/</code>	Move a file to a directory
<code>rm myfile</code>	Delete a file
<code>pv myfile &gt; myfile2</code>	Copy a file, monitoring the progress of data through the pipe
<code>mkdir mydir</code>	Create a directory
<code>mkdir -m 777 mydir</code>	Create a directory with 777 permission
<code>mkdir -p /tmp/mydir1/mydir2</code>	Create a directory, and create also the parent directories if they don't exist
<code>rmdir mydir</code>	Delete a directory (must be empty)
<code>touch myfile</code>	Change access/modification timestamp on a file, creating it if it doesn't exist
<code>ls</code>	List the contents of the current directory
<code>ls -d */</code>	List directories only
<code>stat myfile</code>	Display file or filesystem status
<code>stat -c %A myfile</code>	Display file permissions
<code>stat -c %s myfile</code>	Display file size, in bytes
<code>lsof</code>	List all open files
<code>lsof -u jdoe</code>	List all files currently open by user jdoe
<code>lsof -i</code>	List open files and their sockets (equivalent to <code>netstat -ap</code> )
<code>lsof -i :80</code>	List connections of local processes on port 80
<code>lsof -i@10.0.0.3</code>	List connections of local processes to remote host 10.0.0.3
<code>lsof -i@10.0.0.3:80</code>	List connections of local processes to remote host 10.0.0.3 on port 80
<code>lsof -c mysqld</code>	List all files opened by the MySQL daemon
<code>lsof /var/lib/mysql/mysqld.pid</code>	List all processes which are using a specific file

File-naming wildcards (globbing)	
<code>*</code>	Matches zero or more characters
<code>?</code>	Matches one character
<code>[kxw]</code>	Matches k, x, or w
<code>[!kxw]</code>	Matches any character except k, x, or w
<code>[a-z]</code>	Matches any character between a and z

Brace expansion	
<code>cp myfile.{txt,bak}</code>	Copy myfile.txt to myfile.bak
<code>touch myfile_{a,b,c}</code>	Create myfile_a, myfile_b, myfile_c
<code>touch {a..h}</code>	Create 8 files named a b c d e f g h

In Linux, everything is (displayed as) a file. File descriptors are automatically associated to any process launched.

File descriptors			
#	Name	Type	Default device
0	Standard input (stdin)	Input text stream	Keyboard
1	Standard output (stdout)	Output text stream	Terminal
2	Standard error (stderr)	Output text stream	Terminal

<code>ls   sort</code>	Pipe the stdout of command <code>ls</code> to stdin of command <code>sort</code> (i.e. generate a sorted list of the files on the current directory). Piped commands run concurrently
<code>ls &gt; myfile</code> <code>ls 1&gt; myfile</code>	Redirect the stdout of command <code>ls</code> to a file (i.e. write on a file the content of the current directory). File is overwritten if it already exists; to prevent this, set the Bash noclobber option via <code>set -o noclobber</code>
<code>ls &gt;  myfile</code> <code>ls &gt;&gt; myfile</code> <code>ls 1&gt;&gt; myfile</code>	Redirect the stdout of command <code>ls</code> to a file, even if noclobber is set Append the stdout of command <code>ls</code> to a file
<code>df 2&gt; myfile</code> <code>df 2&gt;&gt; myfile</code>	Redirect the stderr of command <code>df</code> to a file (i.e. write any error encountered by the command <code>df</code> to a file) Append the stderr of command <code>df</code> to a file
<code>mail root@example.com &lt; myfile</code>	Redirect a file to the stdin of command <code>mail</code> (i.e. mail a file to the specified email address)
<code>ls &gt; myfile 2&gt;&amp;1</code> <code>ls &amp;&gt; myfile</code>	Redirect both stdout and stderr of command <code>ls</code> to a file
<code>ls   tee myfile</code> <code>ls   tee -a myfile</code>	<code>tee</code> reads from stdin and writes both to stdout and a file (i.e. write content of current directory to screen and to a file at the same time) <code>tee</code> reads from stdin and appends both to stdout and a file
<code>ls foo*   xargs cat</code>	<code>xargs</code> calls the <code>cat</code> command multiple times for each argument found on stdin (i.e. print the content of every file whose filename starts by foo)
<code>read MYVAR</code> <code>read -n 8 MYVAR</code> <code>read -t 60 MYVAR</code> <code>read -s MYVAR</code> <code>echo \$MYVAR</code> <code>echo -n "message"</code> <code>printf "message"</code>	Read a variable from standard input Read only max 8 chars from standard input Read a variable from standard input, timing out after one minute Read a variable from standard input without echoing to terminal (silent mode) Print a variable on screen Print on screen without a trailing line feed
<code>while read -r line; do echo "Hello \$line"; done &lt; myfile</code>	Process a text file line by line

Any application/program/script that runs on the system is a process. Signals are used for inter-process communication. Each process has a unique PID (Process ID) and a PPID (Parent Process ID); when a process spawns a child, the process PID is assigned to the child's PPID.

The `/sbin/init` process, run at bootup, has PID 1. It is the ancestor of all processes and becomes the parent of any orphaned process. It is also unkillable; should it die, the kernel will panic.

When a child process dies, its status becomes `EXIT_ZOMBIE` and a `SIGCHLD` is sent to the parent. The parent should then call the `wait()` system call to read the dead process' exit status and other info; until that moment, the child process remains a zombie.

<code>ps -ef</code> (UNIX options)	List all processes	
<code>ps aux</code> (BSD options)		
<code>ps tree PID</code>	Display all processes in hierarchical format. The process tree is rooted at PID, or at <code>init</code> if PID is omitted	
<code>top</code> <code>htop</code>	Monitor processes in realtime	
<code>kill -9 1138</code>	Send a signal 9 (SIGKILL) to process 1138, hence killing it	
<code>killall -9 sshd</code>	Kill processes whose name is sshd	
<code>pgrep -u root sshd</code>	Show processes whose name is sshd and are owned by root	Note: <code>pgrep</code> and <code>pkill</code> accept the same options
<code>pkill -9 -u root sshd</code>	Kill processes whose name is sshd and are owned by root	
<code>jobs</code>	List all jobs (i.e. processes whose parent is a Bash shell)	
<b>CTRL</b> <b>Z</b>	Suspend a job, putting it in the stopped state (send a SIGTSTP)	
<code>bg %1</code>	Put job #1 in the background (send a SIGCONT)	
<code>fg %1</code>	Resume job #1 in the foreground and make it the current job (send a SIGCONT)	
<code>kill %1</code>	Kill job #1	

When a Bash shell is terminated cleanly via `exit`, its jobs will become child of the Bash's parent and will continue running. When a Bash is killed instead, it issues a `SIGHUP` to his children which will terminate.

`nohup myscript.sh` Prevent a process from terminating (receiving a `SIGHUP`) when its parent Bash dies

To each process is associated a niceness value: the lower the niceness, the higher the priority. The niceness value ranges from -20 to 19, and a newly created process has a default niceness of 0. Unprivileged users can modify a process' niceness only within the range from 1 to 19.

<code>nice -n -5 command</code>	Start a command with a niceness of -5. If niceness is omitted, a default value of 10 is used
<code>renice -5 command</code>	Change the niceness of a running command to -5
<code>strace command</code>	Trace the execution of a command, intercepting and printing the system calls called by a process and the signals received by a process

Most frequently used signals		
Signal number	Signal name	Meaning
1	SIGHUP	Used by many daemons to reload their configuration
2	SIGINT	Interrupt, stop
9	SIGKILL	Kill unconditionally (this signal cannot be ignored)
15	SIGTERM	Terminate gracefully
18	SIGCONT	Continue execution
20	SIGTSTP	Stop execution

`man 7 signal`      Manual page about signals

`kill -l`      List all available signal names

`kill -l 1`      Print the name of signal number 1

vmstat																
procs		-----memory-----				---swap--		-----io----		--system--			-----cpu-----			
r	b	swpd	free	buff	cache	si	so	bi	bo	in	cs	us	sy	id	wa	st
0	0	0	296724	267120	3393400	0	0	17	56	0	3	2	2	95	1	0

<b>procs</b>	<b>r</b>	Number of runnable processes (running or waiting for run time)														
	<b>b</b>	Number of processes in uninterruptible sleep														
<b>memory</b>	<b>swpd</b>	Virtual memory used (swap)														
	<b>free</b>	Free memory (idle)														
	<b>buff</b>	Memory used as buffers														
	<b>cache</b>	Memory used as cache														
<b>swap</b>	<b>si</b>	Memory swapped in from disk														
	<b>so</b>	Memory swapped out to disk														
<b>io</b>	<b>bi</b>	Blocks received in from a block device														
	<b>bo</b>	Blocks sent out to a block device														
<b>system</b>	<b>in</b>	Number of interrupts														
	<b>cs</b>	Number of context switches														
<b>cpu</b>	<b>us</b>	Time spent running user code (non-kernel)														
	<b>sy</b>	Time spent running system code (kernel)														
	<b>id</b>	Time spent idle														
	<b>wa</b>	Time spent waiting for I/O														
	<b>st</b>	Time stolen from a virtual machine														

```
vmstat
```

Print a report about virtual memory statistics: processes, memory, paging, block I/O, traps, disks, and CPU activity

```
vmstat 1 5
```


Print a report every second, for 5 times



<code>iostat</code>	Print a report about CPU utilization, device utilization, and network filesystem. The first report shows statistics since the system boot; subsequent reports will show statistics since the previous report
<code>iostat -dx 1 5</code>	Print a detailed report for all devices every second, for 5 times
<code>mpstat</code>	Print a report about processor activities
<code>mpstat 1 5</code>	Print a report of global statistics among all processors every second, for 5 times
<code>top</code>	Process viewer
<code>htop</code>	Process viewer (ncurses UI)
<code>iotop</code>	Display I/O usage by processes in the system
<code>free</code>	Show the amount of free and used memory in the system
<code>uptime</code>	Show how long the system has been up, how many users are connected, and the system load averages for the past 1, 5, and 15 minutes
<code>sar</code>	Show reports about system activity. Reports are generated from data collected via the cron job <code>sysstat</code> and stored in <code>/var/log/sa/sn</code> , where <i>n</i> is the day of the month
<code>sar -n DEV</code>	Show reports about network activity (received and transmitted packets per second)
<code>sar -f /var/log/sa/s19 \</code> <code>-s 06:00:00 -e 06:30:00</code>	Show reports for system activity from 6 to 6:30 AM on the 19 <sup>th</sup> of the month
<code>powertop</code>	Power consumption and power management diagnosis tool

Linux monitoring tools	
collectd	System statistics collector
Nagios	System monitor and alert
MRTG	Network load monitor
Cacti	Network monitor

Regular expressions	
<code>^</code>	Beginning of a line
<code>\$</code>	End of a line
<code>\&lt; \&gt;</code>	Word boundaries (beginning of line, end of line, space, or punctuation mark)
<code>.</code>	Any character, except newline
<code>[abc]</code>	Any of the characters specified
<code>[a-z]</code>	Any of the characters in the specified range
<code>[^abc]</code>	Any character except those specified
<code>*</code>	Zero or more times the preceding regex
<code>+</code>	One or more times the preceding regex
<code>?</code>	Zero or one time the preceding regex
<code>{5}</code>	Exactly 5 times the preceding regex
<code>{3,6}</code>	Between 3 and 6 times the preceding regex
<code> </code>	The regex either before or after the vertical bar
<code>( )</code>	Grouping, to be used for back-references. <code>\1</code> expands to the first match, <code>\2</code> for the second, and so on until <code>\9</code>



Permission	Octal value	Command	Effect on file	Effect on directory
<b>Read</b>	user: 400	chmod u+r	Can open and read the file	Can list directory content
	group: 40	chmod g+r		
	others: 4	chmod o+r		
<b>Write</b>	user: 200	chmod u+w	Can modify the file	Can create, delete, and rename files in the directory
	group: 20	chmod g+w		
	others: 2	chmod o+w		
<b>Execute</b>	user: 100	chmod u+x	Can execute the file (binary or script)	Can enter the directory, and search files within (by accessing a file's inode)
	group: 10	chmod g+x		
	others: 1	chmod o+x		
<b>SetUID (SUID)</b>	4000	chmod u+s	Executable is run with the privileges of the file's owner	No effect
<b>SetGID (SGID)</b>	2000	chmod g+s	Executable is run with the privileges of the file's group	All new files and subdirectories inherit the directory's group ID
<b>Sticky</b>	1000	chmod +t	No effect	Only the file's or the directory's owner can delete or rename a file inside

```

chmod 710 file           Set read, write, and execute permission to user; set execute permission to group
chmod u=rwx,g=x file

chmod 660 file           Set read and write permission to user and group
chmod ug=rw file

chmod +wx file           Add write and execute permission to everybody (user, group, and others)
chmod -R o+r file        Add recursively read permission to others
chmod o-x file           Remove execute permission from others

chown root file          Change the owner of file to root
chown root:mygroup file  Change the owner of file to root, and the group of file to mygroup

chgrp mygroup file       Change the group of file to mygroup

```

The `chmod`, `chown`, and `chgrp` commands accept the option `-R` to recursively change properties of files and directories.

```
umask 022
```

Set the permission mask to 022, hence masking write permission for group and others. Linux default permissions are 0666 for files and 0777 for directories. These base permissions are ANDed with the inverted umask value to calculate the final permissions of a new file or directory.

```

chattr +mode file    Add a file or directory attribute
chattr -mode file    Remove a file or directory attribute
chattr =mode file    Set a file or directory attribute, removing all other attributes
lsattr file          List file or directory attributes

```

Mode	Effect
a	File can only be open in append mode for writing
A	When file is accessed, its atime record is not modified
c	File is automatically compressed on-the-fly on disk by the kernel
C	File is not subject to copy-on-write updates (only for filesystems which perform copy-on-write)
d	File will not be backed up by the <code>dump</code> program
D	When directory is modified, changes are written synchronously on disk (equivalent to <code>dirsync</code> mount option)
e	File is using extents for mapping the blocks on disk
E	Compression error on file (attribute is used by experimental compression patches)
h	File is storing its blocks in units of filesystem blocksize instead of in units of sectors, and was larger than 2 Tb
i	File is immutable: cannot be modified, linked, or changed permissions
I	Directory is being indexed using hashed trees
j	All file data is written to the ext3 or ext4 journal before being written to the file itself
N	File has data stored inline within the inode itself
s	File will be securely wiped by zeroing when deleted
S	When file is modified, changes are written synchronously on disk (equivalent to <code>sync</code> mount option)
t	File won't have EOF partial block fragment merged with other files (only for filesystems supporting tail-merging)
T	Directory is the top of directory hierarchies for the purpose of the Orlov block allocator
u	After file is deleted, it can be undeleted
X	Raw contents of compressed file can be accessed directly (attribute is used by experimental compression patches)
Z	Compressed file is dirty (attribute is used by experimental compression patches)

A Linux directory contains a list of structures which are associations between a filename and an inode. An inode contains all file metadata: file type, permissions, owner, group, size, access/change/modification/deletion times, number of links, attributes, ACLs, and address where the actual file content (data) is stored. An inode does not contain the name of the file; this information is stored in the directory the file is in.

`ls -li` Show a listing of the directory with the files' inode numbers

`df -li` Report filesystem inode usage

	Hard link	Symbolic or soft link
<b>Definition</b>	A link to an already existing inode	A path to a filename; a shortcut
<b>Command to create it</b>	<code>ln myfile hardlink</code>	<code>ln -s myfile symlink</code>
<b>Is the link still valid if the original file is moved or deleted?</b>	Yes (because the link references the inode the original file pointed to)	No (the path now references a non-existent file)
<b>Can link to a file in another filesystem?</b>	No (because inode numbers make sense only within a determinate filesystem)	Yes
<b>Can link to a directory?</b>	No	Yes
<b>Link permissions</b>	Reflect the original file's permissions, even when these are changed	<code>rxwxrwxrwx</code>
<b>Link attributes</b>	- (regular file)	<code>l</code> (symbolic link)
<b>Inode number</b>	The same as the original file	A new inode number

<code>find / -name "foo*"</code>	Find all files, starting from the root dir, whose name start with foo
<code>find / -name "foo*" -print</code>	Find all files whose name start with foo and print their path
<code>find / -name "foo*" -exec chmod 700 {} \;</code>	Find all files whose name start with foo and apply permission 700 to all of them
<code>find / -name "foo*" -ok chmod 700 {} \;</code>	Find all files whose name start with foo and apply permission 700 to all of them, asking for confirmation before each file
<code>find / -perm -4000 -type f</code>	Find all files with SUID set (a possible security risk, because a shell with SUID root is a backdoor)
<code>find / -perm -2000 -type f</code>	Find all files with SGID set
 <code>locate ls</code> <code>slocate ls</code>	 Locate the command <code>ls</code> by searching the file index, not by actually walking the filesystem. The search is quick but will only held results relative to the last rebuilding of the file index ( <code>/etc/updatedb.conf</code> )
<code>updatedb</code>	Build the file index ( <code>/etc/updatedb.conf</code> )
 <code>which command</code> <code>which -a command</code>	 Locate a binary executable <code>command</code> within the PATH Locate all matches of <code>command</code> , not only the first one
 <code>whereis command</code> <code>whereis -b command</code> <code>whereis -s command</code> <code>whereis -m command</code>	 Locate the binary, source, and manpage files for <code>command</code> Locate the binary files for <code>command</code> Locate the source files for <code>command</code> Locate the manpage files for <code>command</code>
 <code>file myfile</code>	 Analyze the content of a file or directory
 <code>type command</code>	 Determine if <code>command</code> is a program or a builtin (i.e. a feature internal to the shell)

Bash shell event	Files run	
When a login shell is launched	/etc/profile ~/.bash_profile ~/.bash_login ~/.profile	The shell executes the system-wide profile file, then the first of the 3 user files that exists and is readable
When a login shell exits	~/.bash_logout	
When a non-login shell is launched	/etc/bash.bashrc /etc/bashrc ~/.bashrc	

```
MYVAR=value
((MYVAR=value))
```

Set a variable

```
MYVAR=$((MYVAR+1))
((MYVAR=MYVAR+1))
((MYVAR+=1))
((MYVAR++))
let "MYVAR=MYVAR+1"
let "MYVAR+=1"
let MYVAR++
```

Increment a numeric variable

```
unset MYVAR
export MYVAR
set ${MYVAR:=value}
MYVAR=${MYVAR:-value}
```

Delete a variable

Export a variable so it can be seen by Bash child processes

Set a variable, if it is not already set (i.e. does not exist) or is null

```
echo $MYVAR
echo ${MYVAR:-message}
echo ${MYVAR:+message}
echo $((3+3))
```

Print the value of a variable

If variable exists and is not null, print its value, otherwise print a message

If variable exists and is not null, print a message, otherwise print nothing

Evaluate an expression and print the result

```
set
set -o
set -option
set -o long_option
set +option
set +o long_option
```

Display all Bash variables

Show the status of all Bash options

Enable a Bash option

Disable a Bash option

```
set -v
set -o verbose
set -x
set -o xtrace
```

Enable printing of shell input lines as they are read

Enable printing of command traces before execution of each command

```
env
typeset -f
```

Display all environment variables

Show functions defined in the current Bash session

```
alias ls='ls -lap'
alias
\ls
/bin/ls
```

Set up an alias for the `ls` command

Show defined aliases

Run the non-aliased version of the `ls` command

Scripts must start with the shebang line `#!/bin/bash` indicating the location of the script interpreter.

Script execution	
<code>source myscript.sh</code> <code>. myscript.sh</code>	Script execution takes place in the same shell. Variables defined and exported in the script are seen by the shell when the script exits
<code>bash myscript.sh</code> <code>./myscript.sh</code> (file must be executable)	Script execution spawns a new shell

<code>command &amp;</code>	Execute a command in the background
<code>command1; command2</code>	Execute command 1 and then command 2
<code>command1 &amp;&amp; command2</code>	Execute command 2 only if command 1 executed successfully (exit status = 0)
<code>command1    command2</code>	Execute command 2 only if command 1 did not execute successfully (exit status > 0)
<code>(command1 &amp;&amp; command2)</code>	Group commands together for evaluation priority
<code>exit</code>	Terminate a script
<code>exit n</code>	Terminate a script with the specified exit status number <i>n</i> . By convention, a 0 exit status is used if the script executed successfully, non-zero otherwise
<code>if [ \$? -eq 0 ]</code> <code>then</code> <code>echo "Success"</code> <code>else</code> <code>echo "Fail"</code> <code>fi</code>	Evaluate whether the last executed command exited successfully or failed
<code>function myfunc { commands }</code> <code>myfunc() { commands }</code>	Define a function
<code>myfunc arg1 arg2 ...</code>	Call a function
<code>MYVAR=`date`</code> <code>MYVAR=\$(date)</code>	Assign to a variable the output resulting from a command
<code>for DIR in `ls`</code> <code>do</code> <code>rmdir \$DIR</code> <code>done</code>	Loop through a list of directories
<code>zenity</code>	Display GTK+ graphical dialogs for user messages and input
<code>command   ts</code>	Prepend a timestamp to each line of a command's output

Bash built-in variables	
<code>\$0</code>	Script name
<code>\$n</code>	<i>n</i> th argument passed to the script or function
<code>\$#</code>	Number of arguments passed to the script or function
<code>\$?</code>	Exit status of the last executed command
<code>\${PIPESTATUS[n]}</code>	Exit status of the <i>n</i> th command in the executed pipeline
<code>\$\$</code>	PID of the script in which this variable is called



```
test $MYVAR = "value" && command
[ $MYVAR = "value" ] && command
if [ $MYVAR = "value" ]; then command; fi
```

Perform a test; if it holds true, the command is executed

Test operators		
Integer operators	File operators	Expression operators
-eq      Equal to	-e or -a    Exists	-a      Logical AND
-ne      Not equal to	-d      Is a directory	-o      Logical OR
-lt      Less than	-b      Is a block special file	!      Logical NOT
-le      Less than or equal to	-c      Is a character special file	\ ( \ )    Priority
-gt      Greater than	-f      Is a regular file	
-ge      Greater than or equal to	-r      Is readable	
String operators	-w      Is writable	
-z      Is zero length	-x      Is executable	
-n or nothing    Is non-zero length	-s      Is non-zero length	
= or ==      Is equal to	-u      Is SUID	
!=      Is not equal to	-g      Is SGID	
<      Is alphabetically before	-k      Is sticky	
>      Is alphabetically after	-h      Is a symbolic link	

```
expr $MYVAR = "39 + 3"
```

Evaluate an expression (i.e. the variable will hold the value 42)

```
expr string : regex
```

Return the length of the substring matching the regex

```
expr string : \(regex\)
```

Return the substring matching the regex

Evaluation operators			
=      Equal to	+      Plus	<i>string : regex</i>	String matches regex
!=      Not equal to	-      Minus	<i>match string regex</i>	
<      Less than	\*      Multiplied by	<i>substr string pos length</i>	Substring
<=      Less than or equal to	/      Divided by	<i>index string chars</i>	Index of any chars in string
>      Greater than	%      Remainder	<i>length string</i>	String length
>=      Greater than or equal to			

Tests	
<pre>if [test 1] then     [command block 1] elif [test 2] then     [command block 2] else     [command block 3] fi</pre>	<pre>case \$VAR in     [pattern 1]) [command 1] ;;     [pattern 2]) [command 2] ;;     *) [command 3] esac</pre>

Loops			
<pre>while [test] do [command block] done</pre>	<pre>for I in [list] do [command operating on \$I] done</pre>	break	Terminate a loop
		continue	Jump to the next iteration

<code>vi</code>	Vi, text editor
<code>vim</code>	Vi Improved, an advanced text editor
<code>vimdiff file1 file2</code>	Compare two text files
<code>pico</code>	Pico, simple text editor
<code>nano</code>	Nano, simple text editor (GNU clone of Pico)
<code>emacs</code>	GNU Emacs, a GUI text editor
<code>more</code>	Text pager (obsolete)
<code>less</code>	Text pager

less pager commands	
<code>h</code>	Help
<code>g</code>	Go to first line in the file
<code>G</code>	Go to last line in the file
<code>F</code>	Print the end of the file, moving forward as the file grows
<code>-N</code>	Show line numbers
<code>-n</code>	Don't show line numbers
<code>=</code>	Show information about the file
<code>q</code>	Quit

<b>ESC</b>	Go to Command mode		
i	Insert text before cursor		
I	Insert text after line	and go to Insert mode	
a	Append text after cursor		
A	Append text after line		
w	Move to next word	\$	Move to end of line
b	Move to beginning of word	1G	Move to beginning of file i.e. to line 1
e	Move to end of word	G	Move to end of file
O	Move to beginning of line	z <b>RETURN</b>	Make current line the top line of the screen
<b>CTRL</b> <b>G</b>	Show current line and column number		
yy	Copy current line		
p	Paste buffer after current line		
P	Paste buffer before current line		
Yyp	Duplicate current line		
x	Delete current character		
X	Delete before current character		
D	Delete from current character to end of line		
dd	Delete current line		
7dd	Delete 7 lines (almost any command can be prepended by a number to repeat it a number of times)		
u	Undo last command (Vi can undo the last command only, Vim is able to undo several commands)		
.	Repeat last text-changing command		
/string	Search for <i>string</i> forward	n	Search for next match of <i>string</i>
?string	Search for <i>string</i> backwards	N	Search for previous match of <i>string</i>
:5,40s/^/#/	Add a hash character at the beginning of each line, from line 5 to 40		
!!program	Replace line with output from <i>program</i>		
:r file	Read <i>file</i> and insert it after current line		
:X	Encrypt current document (when opening it again, Vi will prompt for the key to encrypt it)		
:w file	Write to <i>file</i>		
:wq	Save changes and quit		
:x			
:q	Quit (only if there are no changes)		
:q!	Abandon all changes and quit		

Option	Effect
ai	Turn on auto indentation
all	Print all option to screen
ap	Print line after commands <code>d c J m :s t u</code>
aw	Automatic write on commands <code>:n ! e# ^^ :rew ^} :tag</code>
bf	Discard control characters from input
<code>dir=tmpdir</code>	Set <i>tmpdir</i> as directory for temporary work files
eb	Precede error messages with a bell
ht=8	Set terminal tab as 8 spaces
ic	Ignore case when searching
lisp	Modify brackets for Lisp compatibility
list	Show tabs and end-of-line characters
magic	Allow pattern matching with special characters
mesg	Enable UNIX terminal messaging
nu	Show line numbers
opt	Speeds output by eliminating automatic Return
<code>para=LIlPLPPQPbpP</code>	Set macro to start paragraphs for <code>{ }</code> operators
prompt	Prompt : for command input
re	Simulate smart terminal on dumb terminal
remap	Accept macros within macros
report	Show largest size of changes on status line
ro	Make file readonly
scroll=11	Set screen size as 11 lines
<code>sh=/bin/bash</code>	Set shell escape to <code>/bin/bash</code>
showmode	Show current mode on status line
slow	Postpone display updates during inserts
sm	Show matching parentheses when typing
sw=8	Set shift width to 8 characters
<code>tags=/usr/lib/tags</code>	Set path for files checked for tags
term	Print terminal type
terse	Print terse messages
timeout	Eliminate 1-second time limit for macros
tl=3	Set significance of tags beyond 3 characters (0 = all)
ts=8	Set tab stops to 8 for text input
wa	Inhibit normal checks before write commands
warn	Warn "No write since last change"
window=24	Set text window as 24 lines
wm=0	Set automatic wraparound 0 spaces from right margin

`:set option` turn on an option

`:set nooption` turn off an option

Options can also be set permanently by including them in `~/.exrc`

```
SHOW DATABASES;
SHOW TABLES;
USE CompanyDatabase;
SELECT DATABASE();
```

Show all existing databases  
Show all tables from the selected database  
Choose which database to use  
Show which database is currently selected

```
CREATE TABLE customers (
  cusid INT NOT NULL AUTO_INCREMENT PRIMARY KEY,
  firstname VARCHAR(32), lastname VARCHAR(32), dob DATE,
  city VARCHAR(24), zipcode VARCHAR(5));

CREATE TABLE payments (
  payid INT NOT NULL AUTO_INCREMENT PRIMARY KEY,
  date DATE, fee INT, bill VARCHAR(128), cusid INT,
  CONSTRAINT FK1 FOREIGN KEY (cusid) REFERENCES customers(cusid));
```

Create tables

```
CREATE INDEX lastname_index ON customers(lastname);
ALTER TABLE customers ADD INDEX lastname_index (lastname);

DESCRIBE customers;

DROP TABLE payments;

DROP DATABASE CompanyDatabase;

ALTER TABLE customers MODIFY city VARCHAR(32);
```

Create a field index for fast search  
Describe the columns of a table  
Delete a table  
Delete a database  
Modify the type of a field

```
INSERT INTO customers (firstname,lastname,dob)
VALUES ('Arthur','Dent',1959-08-01), ('Trillian','',1971-03-19);

DELETE FROM customers WHERE firstname LIKE 'Zaphod';

UPDATE customers SET city = 'London' WHERE zipcode = '00789';
```

Insert a new record in a table  
Delete some records in a table  
Modify data

```
CREATE VIEW cust_view AS
SELECT * FROM customers WHERE city != 'London';
```

Create a view

```
COMMIT;

ROLLBACK;
```

Commit changes to the database  
Rollback the current transaction, canceling any changes done during it

```
START TRANSACTION;
BEGIN;
```

Disable autocommit for this transaction, until a COMMIT or ROLLBACK is issued

```
SELECT * FROM customers;
```

Select all columns from the customers table

```
SELECT firstname, lastname FROM customers LIMIT 5;
```

Select first and last name of customers, showing 5 records only

```
SELECT firstname, lastname FROM customers WHERE zipcode = '00123';
```

Select first and last name of customers whose zip code is 00123

```
SELECT firstname, lastname FROM customers WHERE zipcode IS NOT NULL;
```

Select first and last name of customers with a recorded zip code

```
SELECT * FROM customers ORDER BY lastname, firstname;
```

Select customers in alphabetical order by last name, then first name

```
SELECT * FROM customers ORDER by zipcode DESC;
```

Select customers, sorting them by zip code in reverse order

```
SELECT firstname, lastname, TIMESTAMPDIFF(YEAR,dob,CURRENT_DATE) as AGE
FROM customers;
```

Select first name, last name, and calculated age of customers

```
SELECT DISTINCT city FROM customers;
```

Show all cities but retrieving each unique output record only once

```
SELECT city, COUNT(*) FROM customers GROUP BY city;
```

Show all cities and the number of customers in each city. NULL values are not counted

```
SELECT cusid, SUM(fee) FROM payments GROUP BY cusid;
```

Show all fee payments grouped by customer ID, summed up

```
SELECT cusid, AVG(fee) FROM payments GROUP BY cusid
HAVING AVG(fee)<50;
```

Show the average of fee payments grouped by customer ID, where this average is less than 50

```
SELECT MAX(fee) FROM payments;
```

Show the highest fee in the table

```
SELECT cusid FROM payments t1 WHERE fee =
(SELECT MAX(t2.fee) FROM payments t2 WHERE t1.cusid=t2.cusid);
```

Show the customer ID that pays the highest fee (via a subquery)

```
SELECT @maxfee:=MAX(fee) FROM payments;
SELECT cusid FROM payments t1 WHERE fee = @maxfee;
```

Show the customer ID that pays the highest fee (via a user set variable)

```
SELECT cusid FROM payments WHERE fee >
ALL (SELECT fee FROM payments WHERE cusid = 4242001;
```

Show the customer IDs that pay fees higher than the highest fee paid by customer ID 4242001

```
SELECT * FROM customers WHERE firstname LIKE 'Trill%';
```

Select customers whose first name starts with "Trill"

```
SELECT * FROM customers WHERE firstname LIKE 'F_rd';
```

Select matching customers; the \_ matches a single character

```
SELECT * FROM customers WHERE firstname REGEXP '^Art.*r$';
```

Select customers whose first name matches the regex

```
SELECT firstname, lastname FROM customers WHERE zipcode = '00123'
UNION
SELECT firstname, lastname FROM customers WHERE cusid > 4242001;

SELECT firstname, lastname FROM customers WHERE zipcode = '00123'
INTERSECT
SELECT firstname, lastname FROM customers WHERE cusid > 4242001;

SELECT firstname, lastname FROM customers WHERE zipcode = '00123'
EXCEPT
SELECT firstname, lastname FROM customers WHERE cusid > 4242001;
```

Select customers that satisfy any of the two requirements

Select customers that satisfy both of the two requirements

Select customers that satisfy the first requirement but not the second

```
SELECT customers.lastname, payments.bill  
FROM customers, payments WHERE customers.cusid = payments.cusid;
```

Perform a join (aka inner join) of two tables to select data that are in a relationship

```
SELECT customers.lastname, payments.bill  
FROM customers NATURAL JOIN payments;
```

```
SELECT customers.lastname, payments.bill  
FROM customers JOIN payments USING (cusid);
```

```
SELECT customers.lastname, payments.bill  
FROM customers JOIN payments ON customers.cusid = payments.cusid;
```

```
SELECT * FROM customers CROSS JOIN payments;
```

Perform a Cartesian product (aka cross join) of two tables

```
SELECT customers.lastname, payments.bill  
FROM customers LEFT JOIN payments ON customers.cusid = payments.cusid;
```

Perform a left join (aka left outer join) of two tables, returning records matching the join condition and also records in the left table with unmatched values in the right table

```
SELECT customers.lastname, payments.bill  
FROM customers RIGHT JOIN payments ON customers.cusid = payments.cusid;
```

Perform a right join (aka right outer join) of two tables, returning records matching the join condition and also records in the right table with unmatched values in the left table

```

SELECT Host,User FROM mysql.user;

CREATE USER 'john'@'localhost' IDENTIFIED BY 'p4ssw0rd';

DROP USER 'john'@'localhost';

SET PASSWORD FOR 'john'@'localhost' = PASSWORD('p4ssw0rd');

SET PASSWORD FOR 'john'@'localhost' = '*7E684A3DF6273CD1B6DE53';

SHOW GRANTS FOR 'john'@'localhost';

GRANT ALL PRIVILEGES ON MyDatabase.* TO 'john'@'localhost';

REVOKE ALL PRIVILEGES FROM 'john'@'localhost';

GRANT SELECT ON *.* TO 'john'@'localhost' IDENTIFIED BY 'p4ssw0rd';

FLUSH PRIVILEGES;

```

```

USE MyDatabase; SOURCE mydbbak.sql;

USE MyDatabase; LOAD DATA LOCAL INFILE 'foofile' INTO TABLE foo;

```

```

SELECT * FROM MyDatabase.mytable;
SELECT * FROM MyDatabase.mytable\g
SELECT * FROM MyDatabase.mytable\G

SELECT /*!99999 my comment*/ * FROM MyDatabase.mytable;

\s

\c

```

```

SELECT VERSION();

SELECT CURDATE();
SELECT CURRENT_DATE;

SELECT CURTIME();
SELECT CURRENT_TIME;

SELECT NOW();

SELECT USER();

```

```
\! command
```

```
TEE logfile
```

List MySQL users

Create a MySQL user, setting his password

Delete a MySQL user

Set a password for a MySQL user

Set a password for a MySQL user, specifying its hash instead of the plaintext

Show permissions for a user

Grant permissions to a user

Revoke permissions from a user

Create a MySQL user and set his grants

Reload and commit the grant tables; to be used after any GRANT command

Restore a database from a dump file

Populate a table with data from file (one record per line, values separated by tabs)

Send a statement to the server

Display result in vertical format, showing each record in multiple rows

Insert a comment in the statement

Print status information about the server and the current connection

Cancel current input

Show version of MySQL server

Show current date

Show current time

Show current date and time

Show current logged-in user@host

Run a shell command

Log all I/O of the current MySQL session to the specified logfile



<pre>SHOW VARIABLES; SHOW SESSION VARIABLES; SHOW LOCAL VARIABLES;  SHOW GLOBAL VARIABLES;  SHOW VARIABLES LIKE 'sort_buffer_size';</pre>	<p>Print session variables (affecting the current connection only)</p> <p>Print global variables (affecting the global operations on the server)</p> <p>Print session variables that match the given pattern</p>
<pre>SET sort_buffer_size=10000; SET SESSION sort_buffer_size=10000; SET LOCAL sort_buffer_size=10000; SET @@sort_buffer_size=10000; SET @@session.sort_buffer_size=10000; SET @@local.sort_buffer_size=10000;  SET GLOBAL sort_buffer_size=10000; SET @@global.sort_buffer_size=10000;</pre>	<p>Set a session variable</p> <p>Set a global variable</p>
<pre>SHOW STATUS; SHOW SESSION STATUS; SHOW LOCAL STATUS;  SHOW GLOBAL STATUS;</pre>	<p>Print session status (concerning the current connection only)</p> <p>Print global status (concerning the global operations on the server)</p>
<pre>SHOW WARNINGS;  SHOW ERRORS;</pre>	<p>Print warnings, errors and notes resulting from the most recent statement in the current session that generated messages</p> <p>Print errors resulting from the most recent statement in the current session that generated messages</p>
<pre>SHOW TABLE STATUS;  SHOW ENGINE INNODB STATUS;</pre>	<p>Print information about the database e.g. engine (InnoDB or MyISAM), rows, indexes, data</p> <p>Print statistics concerning the InnoDB engine</p>
<pre>SHOW FULL PROCESSLIST;</pre>	<p>Print the list of threads running on the system</p>
<pre>SELECT table_schema "Name", sum(data_length+index_length)/1024 "Size Kb" FROM information_schema.TABLES GROUP BY table_schema;</pre>	<p>Display the sizes of all databases in the system</p>

```
mysqld_safe
```

Start the MySQL server (mysqld) with safety features such as restarting the server if errors occur and logging runtime information to the error logfile. Recommended

```
mysql_install_db (deprecated)  
mysqld --initialize
```

Initialize the MySQL data directory, create system tables, and set up an administrative account

```
mysql_secure_installation
```

Set password for root, remove anonymous users, disable remote root login, and remove test database

```
mysql -u root -p  
mysql -u root -ps3cr3t  
mysql -u root -p -e 'CREATE DATABASE MyDatabase'
```

Login to MySQL as root and prompt for the password

Login to MySQL as root with password s3cr3t

Run a SQL command via MySQL

```
mysqldump -u root -p --all-databases > alldbsbak.sql  
mysqldump -u root -p MyDatabase > mydbbak.sql  
mysql -u root -p < alldbsbak.sql  
mysql -u root -p MyDatabase < mydbbak.sql
```

Backup all databases to a dump file

Backup a database to a dump file

Restore all databases from a dump file

Restore a database from a dump file

```
mysql_upgrade -u root -p
```

Check all tables in all databases for incompatibilities with the current version of MySQL

```
mysqlcheck [options]
```

Perform table maintenance. Each table is locked while is being processed. Options are:

--check	Check table for errors (default)
--analyze	Analyze table
--optimize	Optimize table
--repair	Repair table; this can fix almost anything except unique keys that are not unique

```
mysqlcheck --check db table
```

Check the specified table of the specified database

```
mysqlcheck --check --databases db1 db2
```

Check the specified databases

```
mysqlcheck --check --all-databases
```

Check all databases

```
mysqltuner.pl
```

Review the current MySQL installation for performances and stability

Display Managers		
Display Manager	Configuration files	Display Manager greeting screen
xdm <b>X Display Manager</b>	/etc/x11/xdm/Xaccess    Control inbound requests from remote hosts /etc/x11/xdm/Xresources    Configuration settings for X applications and the login screen /etc/x11/xdm/Xservers    Association of X displays with local X server software, or with X terminals via XDMCP /etc/x11/xdm/Xsession    Script launched by xdm after login /etc/x11/xdm/Xsetup_0    Script launched before the graphical login screen /etc/x11/xdm/xdm-config    Association of all xdm configuration files	Defined in /etc/x11/xdm/Xresources by the line: xlogin*greeting: \ Debian GNU/Linux (CLIENTHOST)
gdm <b>GNOME Display Manager</b>	/etc/gdm/gdm.conf or /etc/gdm/custom.conf	Configured via gdmsetup
kdm <b>KDE Display Manager</b>	/etc/kde/kdm/kdmrc	Configured via kdm_config

```
/etc/init.d/xdm start
/etc/init.d/gdm start
/etc/init.d/kdm start
```

Start the X Display Manager

```
xorgconfig            (Debian)
Xorg -configure      (Red Hat)
```

Configure X (text mode)

```
xorgcfg              (Debian)
system-config-display (Red Hat)
```

Configure X (graphical mode)

```
X -version
```

Show which version of X is running

```
xdpyinfo
```

Display information about the X server

```
xwininfo
```

Display information about windows

```
xhost + 10.3.3.3
xhost - 10.3.3.3
```

Add or remove 10.3.3.3 to the list of hosts allowed to make X connections to the local machine

```
switchdesk gde
```

Switch to the GDE Display Manager at runtime

```
/etc/X11/xorg.conf
```

Configuration file for X

```
~/.Xresources
```

Configuration settings for X applications, in the form  
*program\*resource: value*

```
$DISPLAY
```

Environment variable defining the display name of the X server, in the form  
*hostname:displaynumber.screennumber*

/etc/inittab instructs init to launch XDM at runlevel 5:

```
x:5:respawn:/usr/X11R6/bin/xdm -nodaemon
```

/etc/sysconfig/desktop defines GNOME as the default Display Environment and Display Manager:

```
desktop="gde"
displaymanager="gdm"
```

<code>xdotool</code>	X automation tool
<code>xdotool getwindowfocus</code>	Get the ID of the currently focused window (usually the terminal where this command is typed)
<code>xdotool selectwindow</code>	Pop up a X cursor and get the ID of the window selected by it
<code>xdotool key --window 12345678 Return</code>	Simulate a Return keystroke inside window ID 12345678
 <code>xprop</code>	 X property displayer
 <code>xrandr --output eDP1 --right-of VGA1</code>	 Extend the screen on an additional VGA physical screen situated to the left
 <code>xsel</code>	 Manipulate the X selection (primary, secondary, and clipboard)
<code>xsel -b &lt; file</code>	Put the contents of a file in the X clipboard
<code>xsel -b -a &lt; file2</code>	Append the contents of a file to the X clipboard
<code>xsel -b -o</code>	Output onscreen the contents of the X clipboard
 <code>mkfontdir</code>	 Catalog the newly installed fonts in the new directory
<code>xset fp+ /usr/local/fonts</code>	Dynamically add the new installed fonts in <code>/usr/local/fonts</code> to the X server
 <code>xf86</code>	 Start the X font server
<code>fc-cache</code>	Install fonts and build font information cache

Main		Latin 1				Latin 2	
BackSpace	ff08	space	0020	questiondown	00bf	Aogonek	01a1
Tab	ff09	exclam	0021	Agrave	00c0	breve	01a2
Linefeed	ff0a	quotedbl	0022	Aacute	00c1	Lstroke	01a3
Clear	ff0b	numbersign	0023	Acircumflex	00c2	Lcaron	01a5
Return	ff0d	dollar	0024	Atilde	00c3	Sacute	01a6
Pause	ff13	percent	0025	Adiaeresis	00c4	Scaron	01a9
Scroll_Lock	ff14	ampersand	0026	Aring	00c5	Scedilla	01aa
Sys_Req	ff15	apostrophe	0027	AE	00c6	Tcaron	01ab
Escape	ff1b	quoteright	0027	Ccedilla	00c7	Zacute	01ac
Delete	ffff	parenleft	0028	Egrave	00c8	Zcaron	01ae
Cursor control		parenright	0029	Eacute	00c9	Zabovedot	01af
		asterisk	002a	Ecircumflex	00ca	aogonek	01b1
Home	ff50	plus	002b	Ediaeresis	00cb	ogonek	01b2
Left	ff51	comma	002c	Igrave	00cc	lstroke	01b3
Up	ff52	minus	002d	Iacute	00cd	lcaron	01b5
Right	ff53	period	002e	Icircumflex	00ce	sacute	01b6
Down	ff54	slash	002f	Idiaeresis	00cf	caron	01b7
Prior	ff55	0 - 9	0030 - 0039	ETH	00d0	scaron	01b9
Page_Up	ff55	colon	003a	Eth	00d0	scedilla	01ba
Next	ff56	semicolon	003b	Ntilde	00d1	tcaron	01bb
Page_Down	ff56	less	003c	Ograve	00d2	zacute	01bc
End	ff57	equal	003d	Oacute	00d3	doubleacute	01bd
Begin	ff58	greater	003e	Ocircumflex	00d4	zcaron	01be
Misc functions		question	003f	Otilde	00d5	zabovedot	01bf
		at	0040	Odiaeresis	00d6	Racute	01c0
Select	ff60	A - Z	0041 - 005a	multiply	00d7	Abreve	01c3
Print	ff61	bracketleft	005b	Oslash	00d8	Lacute	01c5
Execute	ff62	backslash	005c	Ooblique	00d8	Cacute	01c6
Insert	ff63	bracketright	005d	Ugrave	00d9	Ccaron	01c8
Undo	ff65	asciicircum	005e	Uacute	00da	Eogonek	01ca
Redo	ff66	underscore	005f	Ucircumflex	00db	Ecaron	01cc
Menu	ff67	grave	0060	Udiaeresis	00dc	Dcaron	01cf
Find	ff68	quoteleft	0060	Yacute	00dd	Dstroke	01d0
Cancel	ff69	a - z	0061 - 007a	THORN	00de	Nacute	01d1
Help	ff6a	braceleft	007b	Thorn	00de	Ncaron	01d2
Break	ff6b	bar	007c	ssharp	00df	Odoubleacute	01d5
Mode_switch	ff7e	braceright	007d	agrave	00e0	Rcaron	01d8
script_switch	ff7e	asciitilde	007e	aacute	00e1	Uring	01d9
Num_Lock	ff7f	nobreakspace	00a0	acircumflex	00e2	Udoubleacute	01db
Modifiers		exclamdown	00a1	atilde	00e3	Tcedilla	01de
		cent	00a2	adiaeresis	00e4	racute	01e0
Shift_L	ffe1	sterling	00a3	aring	00e5	abreve	01e3
Shift_R	ffe2	currency	00a4	ae	00e6	lacute	01e5
Control_L	ffe3	yen	00a5	ccedilla	00e7	cacute	01e6
Control_R	ffe4	brokenbar	00a6	egrave	00e8	ccaron	01e8
Caps_Lock	ffe5	section	00a7	eacute	00e9	eogonek	01ea
Shift_Lock	ffe6	diaeresis	00a8	ecircumflex	00ea	ecaron	01ec
Meta_L	ffe7	copyright	00a9	ediaeresis	00eb	dcaron	01ef
Meta_R	ffe8	ordfeminine	00aa	igrave	00ec	dstroke	01f0
Alt_L	ffe9	guillemotleft	00ab	iacute	00ed	ncacute	01f1
Alt_R	ffea	notsign	00ac	icircumflex	00ee	ncaron	01f2
Super_L	ffeb	hyphen	00ad	idiaeresis	00ef	odoubleacute	01f5
Super_R	ffec	registered	00ae	eth	00f0	rcaron	01f8
Hyper_L	ffed	macron	00af	ntilde	00f1	uring	01f9
Hyper_R	ffee	degree	00b0	ograve	00f2	udoubleacute	01fb
		plusminus	00b1	oacute	00f3	tcedilla	01fe
		twosuperior	00b2	ocircumflex	00f4	abovedot	01ff
		threesuperior	00b3	otilde	00f5		
		acute	00b4	odiaeresis	00f6		
		mu	00b5	division	00f7		
		paragraph	00b6	oslash	00f8		
		periodcentered	00b7	ooblique	00f8		
		cedilla	00b8	ugrave	00f9		
		onesuperior	00b9	uacute	00fa		
		masculine	00ba	ucircumflex	00fb		
		guillemotright	00bb	udiaeresis	00fc		
		onequarter	00bc	yacute	00fd		
		onehalf	00bd	thorn	00fe		
		threequarters	00be	ydiaeresis	00ff		

This is an excerpt of `keysymdef.h` which defines keysym codes (i.e. characters or functions associated with each key in X11) as `XX_key` and the `key` hex value. These keys can be used as argument for the `xdotool key` command.

<code>/etc/passwd</code> <b>User accounts</b>	
<pre> root:x:0:0:/root:/bin/bash bin:x:1:1:/bin:/bin/bash jdoe:x:500:100:John Doe,,555-1234,,:/home/jdoe:/bin/bash </pre>	
<b>1</b>	<b>2 3 4 5 6 7</b>
<b>1</b>	Login name
<b>2</b>	Encrypted password (obsolete), or x if password is in <code>/etc/shadow</code>
<b>3</b>	UID – User ID (UID 0 is superuser; by convention UIDs 1-99 are system accounts, UIDs above are regular users)
<b>4</b>	GID – Default Group ID
<b>5</b>	GECOS field – Information about the user: Full name, Room number, Work phone, Home phone, Other
<b>6</b>	Home directory of the user
<b>7</b>	Login shell (can be set to <code>/bin/false</code> to prevent a user from logging in)

<code>/etc/shadow</code> <b>User passwords (readable only by root)</b>	
<pre> root:fZPe54/Kldu6D32p10X/A:15537:0:99999:7::: bin*:15637:0:99999:7::: jdoe:!hsp\8e3jCUdw9Ru53:15580:0:99999:7::15766: </pre>	
<b>1</b>	<b>2 3 4 5 6 7 8 9</b>
<b>1</b>	Login name
<b>2</b>	Encrypted password (a ! prefix if the account is locked, * if account is disabled, ! or !! if no password)
<b>3</b>	Date of last password change (in number of days since 1 January 1970)
<b>4</b>	Days before password may be changed; if 0, user can change the password at any time
<b>5</b>	Days after which password must be changed
<b>6</b>	Days before password expiration that user is warned
<b>7</b>	Days after password expiration that account is disabled
<b>8</b>	Date of account disabling (in number of days since 1 January 1970)
<b>9</b>	Reserved field

<code>/etc/group</code> <b>Group accounts</b>	
<pre> root:x:0:root jdoe:x:501 staff:x:530:jdoe,asmith </pre>	
<b>1</b>	<b>2 3 4</b>
<b>1</b>	Group name
<b>2</b>	Encrypted password, or x if password is in <code>/etc/gshadow</code>
<b>3</b>	GID – Group ID
<b>4</b>	Group members (if this is not their Default Group)

<code>/etc/gshadow</code> <b>Group passwords (readable only by root)</b>	
<pre> root::root:root jdoe::: staff:0cfz7IpLhW19i::root,jdoe </pre>	
<b>1</b>	<b>2 3 4</b>
<b>1</b>	Group name
<b>2</b>	Encrypted password, or ! if no password set (default)
<b>3</b>	Group administrators
<b>4</b>	Group members

<code>useradd -m jdoe</code>	Create a user account, creating and populating his homedir from <code>/etc/skel</code>
<code>useradd -mc "John Doe" jdoe</code>	Create a user account, specifying his full name
<code>useradd -ms /bin/ksh jdoe</code>	Create a user account, specifying his login shell
<code>useradd -D</code>	Show default values (specified in <code>/etc/login.defs</code> ) for user account creation
<code>usermod -c "Jonas Doe" jdoe</code>	Modify the GECOS field of a user account
<code>usermod -L jdoe</code>	Lock a user account
<code>usermod -U jdoe</code>	Unlock a user account
<code>userdel -r jdoe</code>	Delete a user and his homedir
<code>chfn jdoe</code>	Change the GECOS field of a user
<code>chsh jdoe</code>	Change the login shell of a user
<code>passwd jdoe</code>	Change the password of a user
<code>passwd -l jdoe</code>	Lock a user account
<code>passwd -S jdoe</code>	Get information about a user account. Prints username, account status (L=locked, P=password, NP=no password), date of last password change, min age, max age, warning period, inactivity period in days
<code>chage -E 2013-02-14 jdoe</code>	Change the password expiration date, locking the account at that date
<code>chage -d 13111 jdoe</code>	Change the date (in number of days since 1 January 1970) of last password change
<code>chage -d 0 jdoe</code>	Force the user to change password at his next login
<code>chage -M 30 jdoe</code>	Change the max number of days during which a password is valid
<code>chage -m 7 jdoe</code>	Change the min number of days between password changes
<code>chage -W 15 jdoe</code>	Change the number of days before password expiration that the user will be warned
<code>chage -I 3 jdoe</code>	Change the number of days after password expiration before the account is locked
<code>chage -l jdoe</code>	List password aging information for a user
<code>groupadd staff</code>	Create a group
<code>groupmod -n newstaff staff</code>	Change a group name
<code>groupdel staff</code>	Delete a group
<code>gpasswd staff</code>	Set or change the password of a group
<code>gpasswd -a jdoe staff</code>	Add a user to a group
<code>gpasswd -d jdoe staff</code>	Delete a user from a group
<code>gpasswd -A jdoe staff</code>	Add a user to the list of administrators of the group
<code>adduser</code> <code>deluser</code> <code>addgroup</code> <code>delgroup</code> (Debian)	User-friendly front-ends for user and group management

The Linux Standard Base Core Specification specifies that UIDs from 0 to 99 should be statically allocated by the system and not be created by applications, and UIDs from 100 to 499 should be reserved for dynamic allocation by system administrators and post install scripts. User account UIDs start from 500 (Red Hat) or 1000 (SUSE, Debian).

A process has an effective, saved, and real UID and GID:

Effective UID	Used for most access checks, and as the owner for files created by the process. An unprivileged process can change its effective UID only to either its saved UID or its real UID.
Saved UID	Used when a process running with elevated privileges needs to temporarily lower its privileges. The process changes its effective UID (usually root) to a unprivileged one, and its privileged effective UID is copied to the saved UID. Later, the process can resume its elevated privileges by resetting its effective UID back to the saved UID.
Real UID	Used to identify the real owner of the process and affect the permissions for sending signals. An unprivileged process can signal another process only if the sender's real or effective UID matches the receiver's real or saved UID. Child processes inherit the credentials from the parent, so they can signal each other.

<code>/etc/nologin</code>	If this file exists, <code>login</code> and <code>sshd</code> deny login to the system. Useful to prevent users to log in when doing system maintenance
<code>/etc/login.defs</code>	Definition of default values (UID and GID ranges, mail directory, account validity, password encryption method, and so on) for user account creation
<code>whoami</code>	Print your effective UID
<code>id user</code>	Print real and effective UID and GID of the user
<code>who</code>	Print the list of users logged into the system
<code>w</code>	Print the list of users logged into the system, and what they are doing
<code>last</code>	Print the list of users that logged in and out. Searches through the file <code>/var/log/wtmp</code>
<code>lastb</code>	Print the list of bad login attempts. Searches through the file <code>/var/log/btmp</code>
<code>fail2ban</code>	Scan authentication logs and temporarily ban IP addresses (via firewall rules) that have too many failed password logins
<code>/var/log/auth.log</code>	Logfile containing user logins and authentication mechanisms
<code>/var/log/pwdfail</code>	Logfile containing failed authentication attempts



<code>runuser -u jdoe command</code>	Run a command as user jdoe. Can be launched only by the superuser
<code>su jdoe</code>	Run a shell as user jdoe. If user is not specified, assume root
<code>su -c "fdisk -l"</code>	Pass a single command to the shell
<code>su -</code> <code>su -l</code>	Ensure that the spawned shell is a login shell, hence running login scripts and setting the correct environment variables. Recommended option
<code>sudo fdisk -l</code> <code>sudo -u root fdisk -l</code>	Run a command as root. Sudo commands are logged via syslog on <code>/var/log/auth.log</code> (Debian) or <code>/var/log/secure</code> (Red Hat)
<code>sudo !!</code>	Run again the last command, but this time as root
<code>sudoedit /etc/passwd</code> <code>sudo -e /etc/passwd</code>	Edit a protected file. It is recommended to use this instead of allowing users to sudo text editors as root, which will cause security problems if the editor spawns a shell
<code>visudo</code>	Edit <code>/etc/sudoers</code> , the configuration file that specifies access rights to sudo
<code>gksu -u root -l</code> <code>gksudo -u root gparted</code>	GUI front-ends to <code>su</code> and <code>sudo</code> used to run a X Window command as root. Will pop up a requester prompting the user for root's password

<code>write jdoe</code>	Write interactively a message to the terminal of user jdoe (must be logged in)																								
<code>wall</code>	Write interactively a message to the terminal of all logged in users																								
<code>echo "Hello"   write jdoe</code>	Write a message to the terminal of user jdoe (must be logged in)																								
<code>echo "Hello"   wall</code>	Write a message to the terminal of all logged in users																								
<code>talk jdoe</code>	Open an interactive chat session with user jdoe (must be logged in)																								
<code>mesg y</code> <code>chmod g+w \$(tty)</code>	Allow the other users to message you via <code>write</code> , <code>wall</code> , and <code>talk</code>																								
<code>mesg n</code> <code>chmod g-w \$(tty)</code>	Disallow the other users to message you via <code>write</code> , <code>wall</code> , and <code>talk</code>																								
<code>mesg</code>	Display your current message permission status																								
<code>mesg</code> works by enabling/disabling the group write permission of your terminal device, which is owned by system group <code>tty</code> . The superuser is always able to message users.																									
<code>screen</code>	Screen manager that multiplexes a virtual VT100/ANSI terminal between processes. This command creates a screen session; this is useful to be able later to reattach to a remote SSH session lost because of timeout																								
<code>screen -list</code>	Show the list of detached screen sessions																								
<code>screen -r pid.tty.host</code> <code>screen -r sessionowner/pid.tty.host</code>	Resume a detached screen session																								
<code>screen -R</code>	Resume the last detached screen session																								
<code>echo \$(tty)</code>	Print your terminal device (e.g. <code>/dev/tty1</code> , <code>/dev/pts/1</code> )																								
<code>/etc/issue</code>	Message to be printed before the login prompt. Can contain these escape codes: <table><tr><td><code>\b</code></td><td>Baudrate of line</td><td><code>\o</code></td><td>Domain name</td></tr><tr><td><code>\d</code></td><td>Date</td><td><code>\r</code></td><td>OS release number</td></tr><tr><td><code>\s</code></td><td>System name and OS</td><td><code>\t</code></td><td>Time</td></tr><tr><td><code>\l</code></td><td>Terminal device line</td><td><code>\u</code></td><td>Number of users logged in</td></tr><tr><td><code>\m</code></td><td>Architecture identifier of machine</td><td><code>\U</code></td><td>"n users" logged in</td></tr><tr><td><code>\n</code></td><td>Nodename aka hostname</td><td><code>\v</code></td><td>OS version and build date</td></tr></table>	<code>\b</code>	Baudrate of line	<code>\o</code>	Domain name	<code>\d</code>	Date	<code>\r</code>	OS release number	<code>\s</code>	System name and OS	<code>\t</code>	Time	<code>\l</code>	Terminal device line	<code>\u</code>	Number of users logged in	<code>\m</code>	Architecture identifier of machine	<code>\U</code>	"n users" logged in	<code>\n</code>	Nodename aka hostname	<code>\v</code>	OS version and build date
<code>\b</code>	Baudrate of line	<code>\o</code>	Domain name																						
<code>\d</code>	Date	<code>\r</code>	OS release number																						
<code>\s</code>	System name and OS	<code>\t</code>	Time																						
<code>\l</code>	Terminal device line	<code>\u</code>	Number of users logged in																						
<code>\m</code>	Architecture identifier of machine	<code>\U</code>	"n users" logged in																						
<code>\n</code>	Nodename aka hostname	<code>\v</code>	OS version and build date																						
<code>/etc/issue.net</code>	Message to be printed before the login prompt on a remote session																								
<code>/etc/motd</code>	Message to be printed after a successful login, before execution of the login shell																								

`cron` permits repeated scheduled execution.

If `/etc/cron.allow` exists, only users listed therein can access the service.

If `/etc/cron.deny` exists, all users except those listed therein can access the service.

If none of these files exist, all users can access the service.

```
crontab -e          Edit your user crontab file
crontab -l          List the contents of your crontab file
crontab -e -u jdoe  Edit the crontab file of another user (command available only to the superuser)

/etc/cron.hourly
/etc/cron.daily
/etc/cron.weekly
/etc/cron.monthly
```

Scripts placed in these directories will be automatically executed with the specified periods

/etc/crontab							
#	m	h	dom	mon	dow	user	command
	25	6	*	*	1	root	foo.sh
	*/5	16	*	*	*	root	/opt/myscript.sh
	0,30	7	25	12	*	jdoe	/home/jdoe/bar.sh
	3	17	*	*	1-5	root	baz.sh

every Monday at 6:25 AM  
from 4:00 to 4:55 PM every 5 minutes everyday  
at 7:00 and 7:30 AM on 25<sup>th</sup> December  
at 5:03 PM everyday, from Monday to Friday

<b>m</b>	minutes
<b>h</b>	hours
<b>dom</b>	day of month (1-31)
<b>mon</b>	month (1-12 or jan-dec)
<b>dow</b>	day of week (0-7 or sun-sat; 0=7=Sunday)
<b>user</b>	User as whom the command will be executed
<b>command</b>	Command that will be executed at the specified times

The `crond` daemon checks the `/etc/crontab` system-wide file every minute and executes the command as the specified user at the specified times.  
Each user may also set his own crontab scheduling, which will result in a file `/var/spool/cron/username`. A user's crontab file has the same format, except that the `user` field is not present.

/etc/anacrontab				
#	period	delay	job-identifier	command
	7	10	cron-weekly	/opt/myscript.sh

If the job has not been run in the last 7 days, wait 10 minutes and then execute the command

<b>period</b>	period, in days, during which the command was not executed
<b>delay</b>	delay to wait, in minutes, before execution of the command
<b>job-identifier</b>	job identifier in anacron messages
<b>command</b>	command that will be executed

Anacron jobs are run by `crond`, and permit the execution of periodic jobs on a machine that is not always powered on, such as a laptop.

at permits scheduled execution once.

If `/etc/at.allow` exists, only users listed therein can access the service.

If `/etc/at.deny` exists, all users except those listed therein can access the service.

If none of these files exist, no user except root can access the service.

at 5:00pm tomorrow myscript.sh	
at -f mylistofcommands.txt 5:00pm tomorrow	Execute a command once at the specified time (absolute or relative)
echo "rm file"   at now+2 minutes	
at -l	
atq	List the scheduled jobs
at -d 3	
atrm 3	Remove job number 3 from the list

Locale environment variables		
LANG LANGUAGE	Language, stored in <code>/etc/default/locale</code> . When scripting, <code>LANG=C</code> should be set because this specifies the minimal locale environment for C translation, and guarantees a standard collation and formats for the execution of scripts	<p>These locale variables are in the format <i>language_territory.encoding</i> e.g. <code>en_US.UTF-8</code></p> <p>The list of supported locales is stored in <code>/usr/share/i18n/SUPPORTED</code></p>
LC_CTYPE	Character classification and case conversion	
LC_NUMERIC	Non-monetary numeric formats	
LC_TIME	Date and time formats	
LC_COLLATE	Alphabetical order	
LC_MONETARY	Monetary formats	
LC_MESSAGES	Language and encoding of system messages and user input	
LC_PAPER	Paper size	
LC_NAME	Personal name formats	
LC_ADDRESS	Geographic address formats	
LC_TELEPHONE	Telephone number formats	
LC_MEASUREMENT	Measurement units (metric or others)	
LC_IDENTIFICATION	Metadata about locale	
LC_ALL	Special variable overriding all others	

```
locale
```

Show locale environment variables

```
locale-gen it_IT.UTF-8
```

Generate a locale by compiling a list of locale definition files

```
apt-get install manpages-it language-pack-it
```

Install a different locale (system messages and manpages)

```
iconv -f IS6937 -t IS8859 filein > fileout
```

Convert a text file from a codeset to another

ISO/IEC-8859 is a standard for 8-bit encoding of printable characters.

The first 256 characters in ISO/IEC-8859-1 (Latin-1) are identical to those in Unicode.

UTF-8 encoding can represent every character in the Unicode set, and was designed for backward compatibility with ASCII.

<code>tzselect</code>	
<code>tzconfig</code>	
<code>dpkg-reconfigure tzdata</code>	(Debian)

Set the timezone, stored in `/etc/timezone`

Timezone is also set as a symbolic link from `/etc/localtime` to the correct timezone file in `/usr/share/zoneinfo/`

<code>date</code>	Show current date and time
<code>date -d "9999 days ago"</code>	Calculate a date and show it
<code>date -d "1970/01/01 + 4242"</code>	Convert the number of days passed since 1 January 1970 in a canonical date
<code>date +%F %H:%M:%S</code>	Show current date in the format specified
<code>date -s "20130305 23:30:00"</code>	Set the date
<code>date 030523302013</code>	Set the date, in the format <i>MMDDhhmmYYYY</i>
<code>ntpd</code>	NTP daemon, keeps the clock in sync with Internet time servers
<code>ntpd -q</code>	Synchronize the time once and quit
<code>ntpd -g</code>	Force NTP to start even if clock is off by more than the panic threshold (1000 secs)
<code>ntpd -n -g -q</code>	Start NTP as a non-daemon, force set the clock, and quit
<code>ntpq -p timeserver</code>	Query the time server for a list of peers
<code>ntptime timeserver</code>	Synchronizes the clock with the specified time server
<code>ntptime -b timeserver</code>	Brutally set the clock, without waiting for a slow adjusting
<code>ntptime -q timeserver</code>	Query the time server without setting the clock
<code>hwclock --show</code>	
<code>hwclock -r</code>	Show the hardware clock
<code>hwclock --hctosys</code>	
<code>hwclock -s</code>	Set the system time from the hardware clock
<code>hwclock --systohc</code>	
<code>hwclock -w</code>	Set the hardware clock from system time
<code>hwclock --utc</code>	Indicate that the hardware clock is kept in Coordinated Universal Time
<code>hwclock --localtime</code>	Indicate that the hardware clock is kept in local time

Syslog logging facility:

syslogd	Daemon logging events from user processes
klogd	Daemon logging events from kernel processes

/etc/syslog.conf		
# facility.level		action
*.info;mail.none;authpriv.none		/var/log/messages
authpriv.*		/var/log/secure
mail.*		/var/log/maillog
*.alert		root
*.emerg		*
local5.*		@10.7.7.7
local7.*		/var/log/boot.log

Facility Creator of the message	Level Severity of the message	Action Destination of the message
auth or security†	emerg or panic† (highest)	filename message is written into a logfile
authpriv	alert	
cron	crit	@hostname message is sent to a logger server (via UDP port 514)
daemon	err or error†	
kern	warning or warn†	user1,user2,user3 message is sent to users' consoles
lpr	notice	
mail	info	
mark (for syslog internal use)	debug (lowest)	*
news		message is sent to all logged-in users' consoles
syslog		
user		
uucp		
local0 ... local7 (custom)	none (facility disabled)	

† = deprecated

logger -p auth.info "Message" Send a message to syslogd with the specified facility and priority

man 3 syslog Syslog manpage listing facilities and levels


logrotate Rotate logs (by zipping, renaming, and eventually deleting old logfiles) according to /etc/logrotate.conf

tail -f /var/log/messages Print the end of the message log file, moving forward as the file grows (i.e. read logs in real-time)

/var/log/messages  
/var/log/syslog  
/var/log/kern.log

System and kernel logfiles

journalctl (Red Hat) Query the systemd journal (replacement for /var/log/messages)



<code>~/.forward</code>	Mail address(es) to forward the user's mail to, or mail commands
<code>/etc/aliases</code> <code>/etc/mail/aliases</code>	Aliases database for users on the local machine. Each line has syntax <i>alias: user</i>
<code>/var/spool/mail/user</code>	Inbox for <i>user</i> on the local machine
<code>/var/log/mail.log</code> (Debian) <code>/var/log/maillog</code> (Red Hat)	Mail logs
<code>mail -s "Subject" jdoe@example.org &lt; message.txt</code>	Send a mail message to jdoe@example.org
<code>uuencode binaryfile   mail jdoe@example.org</code>	Send a binary file to jdoe@example.org (not recommended, many mailclients will display the received attachment inline)
<code>mutt -a binaryfile -- jdoe@example.org &lt; /dev/null</code>	Send a binary file to jdoe@example.org using the Mutt MUA
<code>newaliases</code> <code>sendmail -bi</code>	Update the aliases database; must be run after any change to <code>/etc/aliases</code>
<code>mailq</code> <code>exim4 -bp</code>	Examine the mail queue
<code>exim4 -M messageID</code>	Attempt delivery of message
<code>exim4 -Mrm messageID</code>	Remove a message from the mail queue
<code>exim4 -Mvh messageID</code>	See the headers of a message in the mail queue
<code>exim4 -Mvb messageID</code>	See the body of a message in the mail queue
<code>exim4 -Mvc messageID</code>	See a message in the mail queue
<code>exim4 -qf domain</code>	Force a queue run of all queued messages for a <i>domain</i>
<code>exim4 -Rff domain</code>	Attempt delivery of all queued messages for a <i>domain</i>
<code>exim4 -bV</code>	Show version and other info

Mailbox formats		
mbox	Each mail folder is a single file, storing multiple email messages.  Advantages: universally supported, fast search inside a mail folder. Disadvantages: issues with file locking, possible mailbox corruption.	<code>\$HOME/Mail/myfolder</code>
Maildir	Each mail folder is a directory, and contains the subdirectories <code>/cur</code> , <code>/new</code> , and <code>/tmp</code> . Each email message is stored in its own file with a unique filename ID.  The process that delivers an email message writes it to a file in the <code>tmp/</code> directory, and then moves it to <code>new/</code> . The moving is commonly done by hard linking the file to <code>new/</code> and then unlinking the file from <code>tmp/</code> , which guarantees that a MUA will not see a partially written message as it never looks in <code>tmp/</code> . When the MUA finds mail messages in <code>new/</code> it moves them to <code>cur/</code> .  Advantages: fast location/retrieval/deletion of a specific mail message, no file locking needed, can be used with NFS. Disadvantages: some filesystems may not efficiently handle a large number of small files, searching text inside all mail messages is slow	<code>\$HOME/Mail/myfolder/</code>



SMTP commands		
220 smtp.example.com ESMTP Postfix HELO abc.example.org 250 Hello abc.example.org, glad to meet you MAIL FROM: alice@example.org 250 Ok RCPT TO bob@foobar.com 250 Ok RCPT TO eve@foobar.com 250 Ok DATA 354 End data with <CR><LF>.<CR><LF> From: Alice <alice@example.org> To: Bob <bob@foobar.com> Cc: Eve <eve@foobar.com> Date: Wed, 13 August 2014 18:02:43 -0500 Subject: Test message  This is a test message. . 250 OK id=10jReS-0005kT-Jj QUIT 221 Bye	HELO abc.example.org  EHLO abc.example.org  MAIL FROM: alice@example.org RCPT TO: bob@foobar.com  DATA  QUIT RSET  HELP  NOOP   VRFY jdoe@example.org  EXPN mailinglist	Initiate the conversation and identify client host to server  Like HELO, but tell server to use Extended SMTP  Specify mail sender Specify mail recipient  Specify data to send. Ended with a dot on a single line  Disconnect  List all available commands Empty command  Verify the existence of an e-mail address (this command should not be implemented, for security reasons)  Check mailing list membership

SMTP response codes		
first digit	1	Command accepted, but not processed until client sends confirmation
	2	Command successfully completed
	3	Command accepted, but not processed until client sends more information
	4	Command failed due to temporary errors
	5	Command failed due to permanent errors
second digit	0	Syntax error or command not implemented
	1	Informative response in reply to a request for information
	2	Connection response in reply to a data transmission
	5	Status response in reply to a mail transfer operation
third digit	Specifies further the response	
211	System status or help reply	
214	Help message	
220	The server is ready	
221	The server is ending the conversation	
250	The requested action was completed	
251	The specified user is not local, but the server will forward the mail message	
354	Reply to the DATA command. After getting this, start sending the message body	
421	The mail server will be shut down, try again later	
450	The mailbox that you are trying to reach is busy, try again later	
451	The requested action was not done. Some error occurred in the mail server	
452	The requested action was not done. The mail server ran out of system storage	
500	The last command contained a syntax error or the command line was too long	
501	The parameters or arguments in the last command contained a syntax error	
502	The last command is not implemented in the mail server	
503	The last command was sent out of sequence	
504	One of the parameters of the last command is not implemented by the server	
550	The mailbox that you are trying to reach can't be found or you don't have access rights	
551	The specified user is not local; part of message text will contain a forwarding address	
552	The mailbox that you are trying to reach has run out of space, try again later	
553	The mail address that you specified was not syntactically correct	
554	The mail transaction has failed for unknown causes	

Sendmail is distributed as a monolithic binary file.

It used to run SUID `root`, which caused many security problems; recent versions run SGID `smmsp`, the group that has write access on the mail queue. Sendmail uses `smrsh`, a restricted shell, to run some external programs.

`/etc/mail/submit.cf` Sendmail local mail transfer configuration file

`/etc/mail/sendmail.cf` Sendmail MTA configuration file

The `.cf` configuration files are generated from edited `.mc` text files via the `m4` command, e.g.

```
m4 /etc/mail/submit.mc > /etc/mail/submit.cf
```

`/etc/mail/access.db` Access control file to allow or deny access to systems or users

`/etc/mail/local-host-names.db` List of domains that must be considered as local accounts

`/etc/mail/virtusertable.db` Map for local accounts, used to distribute incoming email

`/etc/mail/mailertable.db` Routing table, used to dispatch emails from remote systems

`/etc/mail/domaintable.db` Domain table, used for transitions from an old domain to a new one

`/etc/mail/genericstable.db` Map for local accounts, used to specify a different sender for outgoing mail

`/etc/mail/genericsdomain.db` Local FQDN

The `.db` database files are generated from edited text files via the `makemap` command, e.g.

```
makemap hash /etc/mail/access.db < /etc/mail/access
```

`sendmail -bt` Run Sendmail in test mode

`hoststat` Print statistics about remote hosts usage

`purgestat` Clear statistics about remote host usage

`mailstats` Print statistics about the mailserver

`praliases` Display email aliases

Exim is a free MTA, distributed under open source GPL license.

`/etc/exim.conf`  
`/usr/local/etc/exim/configure` (FreeBSD) Exim4 configuration file

`exinext` Give the times of the next queue run

`exigrep` Search through Exim logfiles

`exicyclog` Rotate Exim logfiles

Postfix is a fast, secure, easy to configure, open source MTA intended as a replacement for Sendmail. It is implemented as a set of small helper daemons, most of which run in a chroot jail with low privileges. The main ones are:

master	Postfix master daemon, always running; starts the other daemons when necessary
nqmgr	Queue manager for incoming and outgoing mail, always running
smtpd	SMTP daemon for incoming mail
smtp	SMTP daemon for outgoing mail
bounce	Manager of bounce messages
cleanup	Daemon that verifies the syntax of outgoing messages before they are handed to the queue manager
local	Daemon that handles local mail delivery
virtual	Daemon that handles mail delivery to virtual users

/var/spool/postfix/incoming	Incoming queue. All new mail entering the Postfix queue is written here by the cleanup daemon. Under normal conditions this queue is nearly empty
/var/spool/postfix/active	Active queue. Contains messages ready to be sent. The queue manager places messages here from the incoming queue as soon as they are available
/var/spool/postfix/deferred	Deferred queue. A message is placed here when all its deliverable recipients are delivered, and for some recipients delivery failed for a transient reason. The queue manager scans this queue periodically and puts some messages into the active queue for a retry
/var/spool/postfix/bounce	Message delivery status report about why mail is bounced (non-delivered mail)
/var/spool/postfix/defer	Message delivery status report about why mail is delayed (non-delivered mail)
/var/spool/postfix/trace	Message delivery status report (delivered mail)

postfix reload	Reload configuration
postconf -e 'mydomain = example.org'	Edit a setting in the Postfix configuration
postconf -l	List supported mailbox lock methods
postconf -m	List supported database types
postconf -v	Increase logfile verbosity
postmap dbtype:textfile	Manage Postfix lookup tables, creating a hashed map file of database type <i>dbtype</i> from <i>textfile</i>
postmap hash:/etc/postfix/transport	Regenerate the transport database
postalias newaliases	Convert /etc/aliases into the aliases database file /etc/aliases.db

<code>/etc/postfix/main.cf</code>	Postfix configuration file
<code>mydomain = example.org</code>	This system's domain
<code>myorigin = \$mydomain</code>	Domain from which all sent mail will appear to originate
<code>myhostname = foobar.\$mydomain</code>	This system's hostname
<code>inet_interfaces = all</code>	Network interface addresses that this system receives mail on. Value can also be <code>localhost</code> , <code>all</code> , or <code>loopback-only</code>
<code>proxy_interfaces = 1.2.3.4</code>	Network interface addresses that this system receives mail on by means of a proxy or NAT unit
<code>mynetworks = 10.3.3.0/24 !10.3.3.66</code>	Networks the SMTP clients are allowed to connect from
<code>mydestination = \$myhostname localhost \$mydomain example.com hash:/etc/postfix/otherdomains</code>	Domains for which Postfix will accept received mail. Value can also be a lookup database file e.g. a hashed map
<code>relayhost = 10.6.6.6</code>	Relay host to which Postfix should send all mail for delivery, instead of consulting DNS MX records
<code>relay_domains = \$mydestination</code>	Sources and destinations for which mail will be relayed. Can be empty if Postfix is not intended to be a mail relay
<code>virtual_alias_domains = virtualex.org virtual_alias_maps = /etc/postfix/virtual  or  virtual_alias_domains = hash:/etc/postfix/virtual</code>	Set up Postfix to handle mail for virtual domains too. The <code>/etc/postfix/virtual</code> file is a hashed map, each line of the file containing the virtual domain email address and the destination real domain email address: <pre> jdoe@virtualex.org      john.doe@example.org ksmith@virtualex.org    kim.smith @virtualex.org          root </pre> The last line is a catch-all specifying that all other email messages to the virtual domain are delivered to the root user on the real domain
<code>mailbox_command = /usr/bin/procmail</code>	Use Procmail as MDA

A line beginning with whitespace or tab is a continuation of the previous line.  
A line beginning with a # is a comment. The # is not a comment delimiter if it is not placed at the beginning of a line.

<code>/etc/postfix/master.cf</code>	Postfix master daemon configuration file
<pre> # service type private unpriv chroot wakeup maxproc command + args smtp      inet  n       -       -       -       -       smtpd pickup    fifo  n       -       -       60      1       pickup cleanup   unix  n       -       -       -       0       cleanup qmgr       fifo  n       -       -       300     1       qmgr rewrite    unix  -       -       -       -       -       trivial-rewrite bounce     unix  -       -       -       -       0       bounce defer      unix  -       -       -       -       0       bounce flush      unix  n       -       -       1000?   0       flush smtp       unix  -       -       -       -       -       smtp showq      unix  n       -       -       -       -       showq error      unix  -       -       -       -       -       error local      unix  -       n       n       -       -       local virtual    unix  -       n       n       -       -       virtual lmtp       unix  -       -       n       -       -       lmtp </pre>	
<b>service</b>	Name of the service
<b>type</b>	Transport mechanism used by the service
<b>private</b>	Whether the service is accessible only by Postfix daemons and not by the whole system. Default is yes
<b>unprivileged</b>	Whether the service is unprivileged i.e. not running as root. Default is yes
<b>chroot</b>	Whether the service is chrooted. Default is yes
<b>wakeup</b>	How often the service needs to be woken up by the master daemon. Default is never
<b>maxproc</b>	Max number of simultaneous processes providing the service. Default is 50
<b>command</b>	Command used to start the service

The - indicates that an option is set to its default value.

Procmail is a regex-based MDA whose main purpose is to preprocess and sort incoming email messages. It is able to work both with the standard mbox format and the Maildir format.

To have all email processed by Procmail, the `~/.forward` file may be edited to contain:

```
"|exec /usr/local/bin/procmail || exit 75"
```

<code>/etc/procmailrc</code>	System-wide recipes
<code>~/.procmailrc</code>	User's recipes
<code>procmail -h</code>	List all Procmail flags for recipes
<code>formail</code>	Utility for email filtering and editing
<code>lockfile</code>	Utility for mailbox file locking
<code>mailstat</code>	Utility for generation of reports from Procmail logs

<code>/etc/procmailrc</code> and <code>~/.procmailrc</code> Procmail recipes	
<code>PATH=\$HOME/bin:/usr/bin:/bin:/usr/sbin:/sbin</code> <code>MAILDIR=\$HOME/Mail</code> <code>DEFAULT=\$MAILDIR/Inbox</code> <code>LOGFILE=\$HOME/.procmaillog</code>	Common parameters, non specific to Procmail
<code>:0h: or :0:</code> <code>* ^From: .* (alice bob)@foobar\.org</code> <code>\$DEFAULT</code>	Flag: match headers (default) and use file locking (highly recommended when writing to a file or a mailbox in mbox format) Condition: match the header specifying the sender address Destination: default mailfolder
<code>:0:</code> <code>* ^From: .*owner@listserv\.com</code> <code>* ^Subject:.*Linux</code> <code>\$MAILDIR/Geekstuff1</code>	Conditions: match sender address and subject headers Destination: specified mailfolder, in mbox format
<code>:0</code> <code>* ^From: .*owner@listserv\.com</code> <code>* ^Subject:.*Linux</code> <code>\$MAILDIR/Geekstuff2/</code>	Flag: file locking not necessary because using Maildir format Conditions: match sender address and subject headers Destination: specified mailfolder, in Maildir format
<code># Blacklisted by SpamAssassin</code> <code>:0</code> <code>* ^X-Spam-Status: Yes</code> <code>/dev/null</code>	Flag: file locking not necessary because blackholing to <code>/dev/null</code> Condition: match SpamAssassin's specific header Destination: delete the message
<code>:0B:</code> <code>* hacking</code> <code>\$MAILDIR/Geekstuff</code>	Flag: match body of message instead of headers
<code>:0HB:</code> <code>* hacking</code> <code>\$MAILDIR/Geekstuff</code>	Flag: match either headers or body of message
<code>:0:</code> <code>* &gt; 256000</code> <code>  /root/myprogram</code>	Condition: match messages larger than 256 Kb Destination: pipe message through the specified program
<code>:0fw</code> <code>* ^From: .*@foobar\.org</code> <code>  /root/myprogram</code>	Flags: use the pipe as a filter (modifying the message), and tell Procmail to wait that the filter finished processing the message
<code>:0c</code> <code>* ^Subject:.*administration</code> <code>! secretary@domain.com</code>  <code>:0:</code> <code>\$MAILDIR/Forwarded</code>	Flag: copy the message and proceed with next recipe Destination: forward to specified email address, and (as ordered by the next recipe) save in the specified mailfolder

The Courier MTA provides modules for ESMTP, IMAP, POP3, webmail, and mailing list services in a single framework.

The `courier-authlib` service must be launched first, then the desired mail service e.g. `courier-imap` for the IMAP service.

<code>imapd</code>	Courier IMAP daemon configuration
<code>/usr/lib/courier-imap/etc/imapd-ssl</code>	Courier IMAPS daemon configuration
<b>or</b>	
<code>/etc/courier/pop3d</code>	Courier POP3 daemon configuration
<code>pop3d-ssl</code>	Courier POP3S daemon configuration
<code>/usr/lib/courier-imap/share/</code>	Directory for public and private keys
<code>mkimapdcert</code>	Generate a certificate for the IMAPS service
<code>mkpop3dcert</code>	Generate a certificate for the POP3 service
<code>makealiases</code>	Create system aliases in <code>/usr/lib/courier/etc/aliases.dat</code> , which is made by processing a <code>/usr/lib/courier/etc/aliases/system</code> text file:
	<pre> root      : postmaster mailer-daemon : postmaster MAILER-DAEMON : postmaster uucp      : postmaster postmaster : admin </pre>

<code>/usr/lib/courier-imap/etc/pop3d</code> Courier POP configuration file	
<code>ADDRESS=0</code>	Address to listen on. 0 means all addresses
<code>PORT=127.0.0.1.900,192.168.0.1.900</code>	Port number connections are accepted on. Accept connections on port 900 on IP addresses 127.0.0.1 and 192.168.0.1
<code>POP3AUTH="LOGIN CRAM-MD5 CRAM-SHA1"</code>	POP authentication advertising SASL (Simple Authentication and Security Layer) capability, with CRAM-MD5 and CRAM-SHA1
<code>POP3AUTH_TLS="LOGIN PLAIN"</code>	Also advertise SASL PLAIN if SSL is enabled
<code>MAXDAEMONS=40</code>	Maximum number of POP3 servers started
<code>MAXPERIP=4</code>	Maximum number of connections to accept from the same IP address
<code>PIDFILE=/var/run/courier/pop3d.pid</code>	PID file
<code>TCPDOPTS="-nodnslookup -noidentlookup"</code>	Miscellaneous <code>couriertcpd</code> options that shouldn't be changed
<code>LOGGEROPTS="-name=pop3d"</code>	<code>courierlogger</code> options
<code>POP3_PROXY=0</code>	Enable or disable proxying
<code>PROXY_HOSTNAME=myproxy</code>	Override value from <code>gethostname()</code> when checking if a proxy connection is required
<code>DEFDOMAIN="@example.com"</code>	Optional default domain. If the username does not contain the first character of <code>DEFDOMAIN</code> , then it is appended to the username. If <code>DEFDOMAIN</code> and <code>DOMAINSEP</code> are both set, then <code>DEFDOMAIN</code> is appended only if the username does not contain any character from <code>DOMAINSEP</code>
<code>POP3DSTART=YES</code>	Flag intended to be read by the system startup script
<code>MAILDIRPATH=Maildir</code>	Name of the maildir directory

<code>/usr/lib/courier-imap/etc/imapd</code> Courier IMAP configuration file	
<code>ADDRESS=0</code>	Address to listen on. 0 means all addresses
<code>PORT=127.0.0.1.900,192.168.0.1.900</code>	Port number connections are accepted on. Accept connections on port 900 on IP addresses 127.0.0.1 and 192.168.0.1
<code>AUTHSERVICE143=imap</code>	Authenticate using a different <code>service</code> parameter depending on the connection's port. This only works with authentication modules that use the <code>service</code> parameter, such as PAM
<code>MAXDAEMONS=40</code>	Maximum number of IMAP servers started
<code>MAXPERIP=20</code>	Maximum number of connections to accept from the same IP address
<code>PIDFILE=/var/run/courier/imapd.pid</code>	File where <code>couriertcpd</code> will save its process ID
<code>TCPDOPTS="-nodnslookup -noidentlookup"</code>	Miscellaneous <code>couriertcpd</code> options that shouldn't be changed
<code>LOGGEROPTS="-name=imapd"</code>	<code>courierlogger</code> options
<code>DEFDOMAIN="@example.com"</code>	Optional default domain. If the username does not contain the first character of <code>DEFDOMAIN</code> , then it is appended to the username. If <code>DEFDOMAIN</code> and <code>DOMAINSEP</code> are both set, then <code>DEFDOMAIN</code> is appended only if the username does not contain any character from <code>DOMAINSEP</code>
<code>IMAP_CAPABILITY="IMAP4rev1 UIDPLUS \ CHILDREN NAMESPACE THREAD=ORDEREDSUBJECT \ THREAD=REFERENCES SORT QUOTA IDLE"</code>	Specifies what most of the response should be to the <code>CAPABILITY</code> command
<code>IMAP_KEYWORDS=1</code>	Enable or disable custom IMAP keywords. Possible values are: 0 disable keywords 1 enable keywords 2 enable keywords with a slower algorithm
<code>IMAP_ACL=1</code>	Enable or disable IMAP ACL extension
<code>SMTP_CAPABILITY=SMTP</code>	Enable the experimental Simple Mail Access Protocol extensions
<code>IMAP_PROXY=0</code>	Enable or disable proxying
<code>IMAP_PROXY_FOREIGN=0</code>	Proxying to non-Courier servers. Re-sends the <code>CAPABILITY</code> command after logging in to remote server. May not work with all IMAP clients
<code>IMAP_IDLE_TIMEOUT=60</code>	How often, in seconds, the server should poll for changes to the folder while in IDLE mode
<code>IMAP_CHECK_ALL_FOLDERS=0</code>	Enable or disable server check for mail in every folder
<code>IMAP_UMASK=022</code>	Set the umask of the server process. This value is passed to the <code>umask</code> command. This feature is mostly useful for shared folders, where the file permissions of the messages may be important
<code>IMAP_ULIMITD=131072</code>	Set the upper limit of the size of the data segment of the server process, in Kb. This value is passed to the <code>ulimit -d</code> command. This feature is used as an additional safety check that should stop any potential DoS attacks that exploit any kind of a memory leak to exhaust all the available memory on the server
<code>IMAP_USELOCKS=1</code>	Enable or disable dot-locking to support concurrent multiple access to the same folder. Strongly recommended when using shared folders
<code>IMAP_SHAREDINDEXFILE=/etc/courier/shared/index</code>	Index of all accessible folders. Normally, this setting should not be changed
<code>IMAP_TRASHFOLDERNAME=Trash</code>	Name of the trash folder
<code>IMAP_EMPTYTRASH=Trash:7,Sent:30</code>	Purge folders i.e. delete all messages from the specified folders after the specified number of days
<code>IMAP_MOVE_EXPUNGE_TO_TRASH=0</code>	Enable or disable moving expunged messages to the trash folder (instead of straight deleting them)
<code>HEADERFROM=X-IMAP-Sender</code>	Make the return address, <code>\$SENDER</code> , being saved in the <code>X-IMAP-Sender</code> mail header. This header gets added to the sent message (but not in the copy of the message saved in the folder)
<code>MAILDIRPATH=Maildir</code>	Name of the mail directory

Dovecot is an open source, security-hardened, fast and efficient IMAP and POP3 server. By default it uses PAM authentication. The script `mkcert.sh` can be used to create self-signed SSL certificates.

<code>/etc/dovecot.conf</code>	Dovecot configuration file
<code>base_dir = /var/run/dovecot/</code>	Base directory where to store runtime data
<code>protocols = imap3 pop3s</code>	Protocols to serve. If Dovecot should use dovecot-auth, this can be set to <code>none</code>
<code>listen = *, [::]</code>	Network interfaces to accept connections on. Here, listen to all IPv4 and IPv6 interfaces
<code>disable_plaintext_auth = yes</code>	Disable LOGIN command and all other plaintext authentications unless SSL/TLS is used (LOGINDISABLED capability)
<code>shutdown_clients = yes</code>	Kill all IMAP and POP3 processes when Dovecot master process shuts down. If set to no, Dovecot can be upgraded without forcing existing client connections to close
<code>log_path = /dev/stderr</code>	Log file to use for error messages, instead of sending them to syslog. Here, log to stderr
<code>info_log_path = /dev/stderr</code>	Log file to use for informational and debug messages. Default value is the same as <code>log_path</code>
<code>syslog_facility = mail</code>	Syslog facility to use if logging to syslog
<code>login_dir = /var/run/dovecot/login</code>	Directory where the authentication process places authentication UNIX sockets, to which the login process needs to be able to connect
<code>login_chroot = yes</code>	Chroot login process to the <code>login_dir</code>
<code>login_user = dovecot</code>	User to use for the login process. This user is used to control access for authentication process, and not to access mail messages
<code>login_process_size = 64</code>	Maximum login process size, in Mb
<code>login_process_per_connection = yes</code>	If yes, each login is processed in its own process (more secure); if no, each login process processes multiple connections (faster)
<code>login_processes_count = 3</code>	Number of login processes to keep for listening for new connections
<code>login_max_processes_count = 128</code>	Maximum number of login processes to create
<code>login_max_connections = 256</code>	Maximum number of connections allowed per each login process. This setting is used only if <code>login_process_per_connection = no</code> ; once the limit is reached, the process notifies master so that it can create a new login process
<code>login_greeting = Dovecot ready.</code>	Greeting message for clients
<code>login_trusted_networks = \ 10.7.7.0/24 10.8.8.0/24</code>	Trusted network ranges (usually IMAP proxy servers). Connections from these IP addresses are allowed to override their IP addresses and ports, for logging and authentication checks. <code>disable_plaintext_auth</code> is also ignored for these networks
<code>mbox_read_locks = fcntl mbox_write_locks = dotlock fcntl</code>	Locking methods to use for locking mailboxes in mbox format. Possible values are: <div> <div>dotlock</div> <div>dotlock_try</div> <div>fcntl</div> <div>flock</div> <div>lockf</div> </div> <div> <div>Create <code>mailbox.lock</code> file; oldest and NSF-safe method</div> <div>Same as <code>dotlock</code>, but skip if failing</div> <div>Recommended; works with NFS too if <code>lockd</code> is used</div> <div>May not exist in all systems; doesn't work with NFS</div> <div>May not exist in all systems; doesn't work with NFS</div> </div>
<code>maildir_stat_dirs = no</code>	Option for mailboxes in Maildir format. If no (default), the LIST command returns all entries in the mail directory beginning with a dot. If yes, returns only entries which are directories
<code>dbx_rotate_size = 2048 dbx_rotate_min_size = 16</code>	Maximum and minimum file size, in Kb, of a mailbox in dbx format until it is rotated
<code>!include /etc/dovecot/conf.d/*.conf</code>	Include configuration file
<code>!include_try /etc/dovecot/extra.conf</code>	Include optional configuration file, do not give error if file not found



<code>/etc/dovecot.conf</code> Dovecot configuration file	
<pre>mail_location = \ mbox:~/mail:INBOX=/var/spool/mail/%u or mail_location = maildir:~/Maildir</pre>	<p>Mailbox location, in mbox or Maildir format. Variables:</p> <ul style="list-style-type: none"> <li>%u username</li> <li>%n user part in <i>user@domain</i>, same as %u if there is no domain</li> <li>%d domain part in <i>user@domain</i>, empty if there is no domain</li> <li>%h home directory</li> </ul>
<pre>namespace shared {      separator = /      prefix = shared/%u/      location = maildir:%h/Maildir:\         INDEX=~/.Maildir/shared/%u      inbox = no      hidden = no      subscriptions = no      list = children  }</pre>	<p>Definition of a shared namespace, for accessing other users' mailboxes that have been shared. Private namespaces are for users' personal emails. Public namespaces are for shared mailboxes managed by root user</p> <p>Hierarchy separator to use. Should be the same for all namespaces; it depends on the underlying mail storage format</p> <p>Prefix required to access this namespace; must be different for each. Here, mailboxes are visible under <i>shared/user@domain/</i>; the variables %n, %d and %u are expanded to the destination user</p> <p>Mailbox location for other users' mailboxes; it is in the same format as <i>mail_location</i> which is also the default for it. %variable and ~/ expand to the logged in user's data; %%variable expands to the destination user's data</p> <p>There can be only one INBOX, and this setting defines which namespace has it</p> <p>Define whether the namespace is hidden i.e. not advertised to clients via NAMESPACE extension</p> <p>Namespace handles its own subscriptions; if set to no, the parent namespace handles them and Dovecot uses the default namespace for saving subscriptions. If <i>prefix</i> is empty, this should be set to yes</p> <p>Show the mailboxes under this namespace with LIST command, making the namespace visible for clients that do not support the NAMESPACE extension. Here, lists child mailboxes but hide the namespace prefix; list the namespace only if there are visible shared mailboxes</p>
<pre>mail_uid = 666 mail_gid = 666</pre>	<p>UID and GID used to access mail messages</p>
<pre>mail_privileged_group = mail</pre>	<p>Group to enable temporarily for privileged operations; currently this is used only with INBOX when its initial creation or a dotlocking fails</p>
<pre>mail_access_groups = tmpmail</pre>	<p>Supplementary groups to grant access to for mail processes; typically these are used to set up access to shared mailboxes</p>
<pre>lock_method = fcntl</pre>	<p>Locking method for index files. Can be <i>fcntl</i>, <i>flock</i>, or <i>dotlock</i></p>
<pre>first_valid_uid = 500 last_valid_uid = 0</pre>	<p>Valid UID range for users; default is 500 and above. This makes sure that users cannot login as daemons or other system users. Denying root login is hardcoded to Dovecot and cannot be bypassed</p>
<pre>first_valid_gid = 1 last_valid_gid = 0</pre>	<p>Valid GID range for users; default is non-root/wheel. Users having non-valid primary GID are not allowed to login</p>
<pre>max_mail_processes = 512</pre>	<p>Maximum number of running mail processes. When this limit is reached, new users are not allowed to login</p>
<pre>mail_process_size = 256</pre>	<p>Maximum mail process size, in Mb</p>
<pre>valid_chroot_dirs =</pre>	<p>List of directories under which chrooting is allowed for mail processes</p>
<pre>mail_chroot =</pre>	<p>Default chroot directory for mail processes. Usually not needed as Dovecot does not allow users to access files outside their mail directory</p>
<pre>mailbox_idle_check_interval = 30</pre>	<p>When IDLE command is running, mailbox is checked once in a while to see if there are any new mails or other changes. This setting defines the minimum time to wait between these checks, in seconds</p>

<code>/etc/dovecot.conf</code> Dovecot configuration file	
<pre>protocol pop3 {     listen = *:110     login_executable = /usr/libexec/dovecot/pop3-login     mail_executable = /usr/libexec/dovecot/pop3     pop3_no_flag_updates = no      pop3_lock_session = no      pop3_uidl_format = %08Xu%08Xv }</pre>	<p>Block with options for the POP3 protocol</p> <p>Network interfaces to accept POP3 connections on</p> <p>Location of the POP3 login executable</p> <p>Location of the POP3 mail executable</p> <p>If set to no, do not try to set mail messages non-recent or seen with POP3 sessions, to reduce disk I/O. With Maildir format do not move files from <code>new/</code> to <code>cur/</code>, with mbox format do not write <code>Status-</code> headers</p> <p>Whether to keep the mailbox locked for the whole POP3 session</p> <p>POP3 UIDL (Unique Mail Identifier) format to use</p>
<pre>protocol imap {     listen = *:143     ssl_listen = *:993      login_executable = /usr/libexec/dovecot/imap-login     mail_executable = /usr/libexec/dovecot/imap     mail_max_userip_connections = 10      imap_idle_notify_interval = 120 }</pre>	<p>Block with options for the IMAP protocol</p> <p>Network interfaces to accept IMAP and IMAPS connections on</p> <p>Location of the IMAP login executable</p> <p>Location of the IMAP mail executable</p> <p>Maximum number of IMAP connections allowed for a user from each IP address</p> <p>How many seconds to wait between "OK Still here" notifications when client is IDLE</p>
<code>ssl = yes</code>	SSL/TLS support. Possible values are <code>yes</code> , <code>no</code> , <code>required</code>
<code>ssl_cert_file = /etc/ssl/certs/dovecot-cert.pem</code>	Location of the SSL certificate
<code>ssl_key_file = /etc/ssl/private/dovecot-key.pem</code>	Location of private key
<code>ssl_key_password = blgs3cr3t</code>	Password of private key, if it is password-protected. Since <code>/etc/dovecot.conf</code> is usually world-readable, it is better to place this setting into a root-owned 0600 file instead and include it via the setting <code>!include_try /etc/dovecot/dovecot-passwd.conf</code> . Alternatively, Dovecot can be started with <code>dovecot -p blgs3cr3t</code>
<code>ssl_ca_file = /etc/dovecot/cafile.pem</code>	List of trusted SSL certificate authorities; the file contains the CA certificates followed by the CRLs
<code>ssl_verify_client_cert = yes</code>	Request client to send a certificate
<code>ssl_cipher_list = ALL:!LOW:!SSLv2</code>	List of SSL ciphers to use
<code>verbose_ssl = yes</code>	Show protocol level SSL errors

<code>/etc/dovecot.conf</code> Dovecot configuration file	
<code>auth_executable = /usr/libexec/dovecot/dovecot-auth</code>	Location of the authentication executable
<code>auth_process_size = 256</code>	Max authentication process size, in Mb
<code>auth_username_chars = abcde...VWXYZ01234567890.-_@</code>	List of allowed characters in the username. If the username entered by user contains a character not listed in here, the login automatically fails. This is to prevent an user exploiting any potential quote escaping vulnerabilities with SQL/LDAP databases
<code>auth_realms =</code>	List of realms for SASL authentication mechanisms that need them. If empty, multiple realms are not supported
<code>auth_default_realm = example.org</code>	Default realm/domain to use if none was specified
<code>auth_anonymous_username = anonymous</code>	Username to assign to users logging in with ANONYMOUS SASL mechanism
<code>auth_verbose = no</code>	Whether to log unsuccessful authentication attempts and the reasons why they failed
<code>auth_debug = no</code>	Whether to enable more verbose logging (e.g. SQL queries) for debugging purposes
<code>auth_failure_delay = 2</code>	Delay before replying to failed authentications, in seconds
<pre>auth default {     mechanisms = plain login cram-md5      passdb passwd-file {         args = /etc/dovecot.deny         deny = yes     }      passdb pam {         args = cache_key=%u%r dovecot     }      passdb passwd {         blocking = yes         args =     }      passdb shadow {         blocking = yes         args =     }      passdb bsdauth {         cache_key = %u         args =     }      passdb sql {         args = /etc/dovecot/dovecot-sql.conf     }      passdb ldap {         args = /etc/dovecot/dovecot-ldap.conf     }      socket listen {         master {             path = /var/run/dovecot/auth-master             mode = 0600             user =             group =         }         client {             path = /var/run/dovecot/auth-client             mode = 0660         }     } }</pre>	<p>Accepted authentication mechanisms</p> <p>Deny login to the users listed in <code>/etc/dovecot.deny</code> (file contains one user per line)</p> <p>PAM authentication block. Enable authentication matching (username and remote IP address) for PAM.</p> <p>System users e.g. NSS or <code>/etc/passwd</code></p> <p>Shadow passwords for system users e.g. NSS or <code>/etc/passwd</code></p> <p>PAM-like authentication for OpenBSD</p> <p>SQL database</p> <p>LDAP database</p> <p>Export the authentication interface to other programs. Master socket provides access to userdb information; it is typically used to give Dovecot's local delivery agent access to userdb so it can find mailbox locations. The default user/group is the one who started <code>dovecot-auth</code> (i.e. root). The client socket is generally safe to export to everyone. Typical use is to export it to the SMTP server so it can do SMTP AUTH lookups using it</p>

**Active mode** (default)

1. Client connects to FTP server on port 21 (control channel) and sends second unprivileged port number
2. Server acknowledges
3. Server connects from port 20 (data channel) to client's second unprivileged port number
4. Client acknowledges

**Passive mode** (more protocol-compliant, because it is the client that initiates the connection)

1. Client connects to FTP server on port 21 and requests passive mode via the PASV command
2. Server acknowledges and sends unprivileged port number via the PORT command
3. Client connects to server's unprivileged port number
4. Server acknowledges

Very Secure FTP is a hardened and high-performance FTP implementation.

The `vsftpd` daemon operates with multiple processes that run as a non-privileged user in a chrooted jail.

/etc/vsftpd/vsftpd.conf	
<code>listen=NO</code>	Run <code>vsftpd</code> in standalone mode (i.e. not via <code>inetd</code> )?
<code>local_enable=YES</code>	Allow local system users (i.e. in <code>/etc/passwd</code> ) to log in?
<code>chroot_local_user=YES</code>	Chroot local users in their home directory?
<code>write_enable=YES</code>	Allow FTP commands that write on the filesystem (i.e. <code>STOR</code> , <code>DELE</code> , <code>RNFR</code> , <code>RNTO</code> , <code>MKD</code> , <code>RMD</code> , <code>APPE</code> and <code>SITE</code> )?
<code>anonymous_enable=YES</code>	Allow anonymous logins? If yes, <code>anonymous</code> and <code>ftp</code> are accepted as logins
<code>anon_root=/var/ftp/pub</code>	After anonymous login, go to directory <code>/var/ftp/pub</code>
<code>anon_upload_enable=YES</code>	Allow anonymous uploads?
<code>chown_uploads=YES</code>	Change ownership of anonymously uploaded files?
<code>chown_username=ftp</code>	Change ownership of anonymously uploaded files to user <code>ftp</code>
<code>anon_world_readable_only=NO</code>	Allow anonymous users to only download files which are world readable?
<code>ssl_enable=YES</code>	Enable SSL?
<code>force_local_data_ssl=NO</code>	Encrypt local data?
<code>force_local_logins_ssl=YES</code>	Force encrypted authentication?
<code>allow_anon_ssl=YES</code>	Allow anonymous users to use SSL?
<code>ssl_tlsv1=YES</code> <code>ssl_tlsv2=NO</code> <code>ssl_tlsv3=NO</code>	Versions of SSL/TLS to allow
<code>rsa_cert_file=/etc/pki/tls/certs/vsftpd.pem</code>	Location of certificate file
<code>rsa_private_key_file=/etc/pki/tls/certs/vsftpd.pem</code>	Location of private key file

Pure-FTP is a free, easy-to-use FTP server.

<code>pure-ftpd</code>	Pure-FTP daemon
<code>pure-ftpwho</code>	Show clients connected to the Pure-FTP server
<code>pure-mrtginfo</code>	Show connections to the Pure-FTP server as a MRTG graph
<code>pure-statsdecode</code>	Show Pure-FTP log data
<code>pure-pw</code>	Manage Pure-FTP virtual accounts
<code>pure-pwconvert</code>	Convert the system user database to a Pure-FTP virtual accounts database
<code>pure-quotacheck</code>	Manage Pure-FTP quota database
<code>pure-uploadsript</code>	Run a command on the Pure-FTP server to process an uploaded file

<code>cupsd</code>	CUPS (Common Unix Printing System) daemon. Administration of printers is done via web interface on <code>http://localhost:631</code>
<code>/etc/cups/cupsd.conf</code>	CUPS configuration file
<code>/etc/cups/printers.conf</code>	Database of available local CUPS printers
<code>/etc/printcap</code>	Database of printer capabilities, for old printing applications
<code>/var/spool/cups/</code>	Printer spooler for data awaiting to be printed
<code>/var/log/cups/error_log</code>	CUPS error log
<code>/var/log/cups/page_log</code>	Information about printed pages
<code>/etc/init.d/cupsys start</code>	Start the CUPS service
<code>gnome-cups-manager</code>	Run the CUPS Manager graphical application
<code>cupsenable printer0</code>	Enable a CUPS printer
<code>cupsdisable printer0</code>	Disable a CUPS printer
<code>cupsaccept printer0</code>	Accept a job sent on a printer queue
<code>cupsreject -r "Rejected" printer0</code>	Reject a job sent on a printer queue, with an informational message
<code>cupstestppd LEXC510.ppd</code>	Test the conformance of a PPD file to the format specification
<code>cupsaddsmb printer0</code>	Export a printer to SAMBA (for use with Windows clients)
<code>cups-config --cflags</code>	Show the necessary compiler options
<code>cups-config --datadir</code>	Show the default CUPS data directory
<code>cups-config --ldflags</code>	Show the necessary linker options
<code>cups-config --libs</code>	Show the necessary libraries to link to
<code>cups-config --serverbin</code>	Show the default CUPS binaries directory that stores filters and backends
<code>cups-config --serverroot</code>	Show the default CUPS configuration file directory
<code>lpstat</code>	Show CUPS status information
<code>lpadmin</code>	Administer CUPS printers
<code>lpadmin -p printer0 -P LEXC750.ppd</code>	Specify a PPD (Adobe PostScript Printer Description) file to associate to a printer
<code>lp -d printer0 file</code>	Print a file on the specified printer
<code>lpq</code>	View the default print queue
<code>lpq -P printer0</code>	View a specific print queue
<code>lpq jdoe</code>	View the print queue of a specific user
<code>lprm -P printer0 5</code>	Delete a specific job from a printer queue
<code>lprm -P printer0 jdoe</code>	Delete all jobs from a specific user from a printer queue
<code>lprm -P printer0 -</code>	Delete all jobs from a printer queue
<code>lpc</code>	Manage print queues
<code>a2ps file.txt</code>	Convert a text file to PostScript
<code>ps2pdf file.ps</code>	Convert a file from PostScript to PDF
<code>mpage file.ps</code>	Print a PostScript document on multiple pages per sheet on a PostScript printer
<code>gv file.ps</code>	View a PostScript document (the gv software is derived from GhostView)

IPv4	
193.22.33.44	32-bit divided in 4 octets (dotted-quad)
	4 billion addresses

IPv6	
2130:0000:0000:0007:0040:15bc:235f	128-bit divided in 8 16-bit sections
2130:0:0:0:7:40:15bc:235f	
2130::7:40:15bc:235f	3 × 10 <sup>38</sup> addresses

IPv4 classful addressing (assigned by IANA)					
		Address range	Prefix	Number of addresses	Reference
Classful	Class A (Unicast)	0.0.0.0 – 127.255.255.255 first octet: 0XXX XXXX	/8	128 networks × 16,777,216 addresses	RFC 791
	Class B (Unicast)	128.0.0.0 – 191.255.255.255 first octet: 10XX XXXX	/16	16,384 networks × 65,536 addresses	RFC 791
	Class C (Unicast)	192.0.0.0 – 223.255.255.255 first octet: 110X XXXX	/24	2,097,152 networks × 256 addresses	RFC 791
	Class D (Multicast)	224.0.0.0 – 239.255.255.255 first octet: 1110 XXXX	/4	268,435,456	RFC 3171
	Class E (Experimental)	240.0.0.0 – 255.255.255.255 first octet: 1111 XXXX	/4	268,435,456	RFC 1166
Private	Private Class A	10.0.0.0 – 10.255.255.255	10.0.0.0/8	16,777,216	RFC 1918
	Private Class B	172.16.0.0 – 172.31.255.255	172.16.0.0/12	1,048,576	RFC 1918
	Private Class C	192.168.0.0 – 192.168.255.255	192.168.0.0/16	65,536	RFC 1918
Reserved	Source	0.0.0.0 – 0.255.255.255	0.0.0.0/8	16,777,216	RFC 1700
	Loopback	127.0.0.0 – 127.255.255.255	127.0.0.0/8	16,777,216	RFC 1700
	Autoconf	169.254.0.0 – 169.254.255.255	169.254.0.0/16	65,536	RFC 3330
	TEST-NET	192.0.2.0 – 192.0.2.255	192.0.2.0/24	256	RFC 3330
	6to4 relay anycast	192.88.99.0 – 192.88.99.255	192.88.99.0/24	256	RFC 3068
	Device benchmarks	198.18.0.0 – 198.19.255.255	198.18.0.0/15	131,072	RFC 2544


VLSM chart - Last octet subnetting (CIDR notation)							
Prefix: /24 Netmask: .0 00000000 1 subnet 254 hosts each 254 total hosts	Prefix: /25 Netmask: .128 10000000 2 subnets 126 hosts each 252 total hosts	Prefix: /26 Netmask: .192 11000000 4 subnets 62 hosts each 248 total hosts	Prefix: /27 Netmask: .224 11100000 8 subnets 30 hosts each 240 total hosts	Prefix: /28 Netmask: .240 11110000 16 subnets 14 hosts each 224 total hosts	Prefix: /29 Netmask: .248 11111000 32 subnets 6 hosts each 192 total hosts	Prefix: /30 Netmask: .252 11111100 64 subnets 2 hosts each 128 total hosts	
.0	.0	.0	.0	.0	.0	.0	
					.16	.8	.4
						.16	.8
						.24	.12
				.28		.16	
				.32	.32	.20	
					.40	.24	
					.48	.28	
			.56		.32		
			.64		.36		
			.72		.40		
			.80		.44		
			.88		.48		
			.64	.64	.96	.52	
					.104	.56	
					.112	.60	
		.120			.64		
		.128			.68		
		.136			.72		
		.144			.76		
		.152			.80		
		.96		.160	.84		
				.168	.88		
				.176	.92		
				.184	.96		
				.192	.100		
				.200	.104		
				.208	.108		
				.216	.112		
		.128	.128	.128	.128	.116	
					.136	.120	
					.144	.124	
	.152				.128		
	.160				.132		
	.168				.136		
	.176				.140		
	.184				.144		
	.160			.192	.148		
				.200	.152		
				.208	.156		
				.216	.160		
				.224	.164		
				.232	.168		
				.240	.172		
				.248	.176		
	.192		.192	.192	.188	.180	
					.192	.184	
					.200	.188	
					.208	.192	
				.208	.216	.196	
					.224	.200	
					.232	.204	
					.240	.208	
			.224	.224	.212	.212	
					.216	.216	
					.224	.220	
					.232	.224	
				.240	.240	.228	
					.248	.232	
						.236	
						.240	

Each block of a column identifies a subnet, whose range of valid hosts addresses is [network address +1 — broadcast address -1] inclusive.

The network address of the subnet is the number shown inside a block.

The broadcast address of the subnet is the network address of the block underneath -1 or, for the bottom block, .255.

Most common well-known ports		
Port number		Service
20	TCP	FTP (data)
21	TCP	FTP (control)
22	TCP	SSH
23	TCP	Telnet
25	TCP	SMTP
53	TCP/UDP	DNS
67	UDP	BOOTP/DHCP (server)
68	UDP	BOOTP/DHCP (client)
80	TCP	HTTP
110	TCP	POP3
119	TCP	NNTP
139	TCP/UDP	Microsoft NetBIOS
143	TCP	IMAP
161	UDP	SNMP
443	TCP	HTTPS (HTTP over SSL/TLS)
465	TCP	SMTP over SSL
993	TCP	IMAPS (IMAP over SSL)
995	TCP	POP3S (POP3 over SSL)
1-1023: privileged ports, used server-side 1024-65535: unprivileged ports, used client-side  The full list of well-known ports is in <code>/etc/services</code>		





<code>ip addr show</code>	Display configuration of all network interfaces
<code>ifconfig -a</code>	
<code>ip link show eth0</code>	Display configuration of eth0
<code>ifconfig eth0</code>	
<code>ip addr add dev eth0 10.1.1.1/8</code>	Configure IP address of eth0
<code>ifconfig eth0 10.1.1.1 netmask 255.0.0.0 broadcast 10.255.255.255</code>	
<code>ifconfig eth0 hw ether 45:67:89:ab:cd:ef</code>	Configure MAC address of eth0
<code>ip link set eth0 up</code>	Activate eth0
<code>ifconfig eth0 up</code>	
<code>ifup eth0</code>	
<code>ip link set eth0 down</code>	Shut down eth0
<code>ifconfig eth0 down</code>	
<code>ifdown eth0</code>	
<code>dhclient eth0</code>	Request an IP address via DHCP
<code>pump</code>	
<code>dhcpcd eth0 (SUSE)</code>	
<code>ip neigh</code>	Show the ARP cache table
<code>arp -a</code>	
<code>ip neigh show 10.1.0.6</code>	Show the ARP cache entry for a host
<code>arp 10.1.0.6</code>	
<code>ip neigh add 10.1.0.7 lladdr 01:23:45:67:89:ab dev eth0</code>	Add a new ARP entry for a host
<code>arp -s 10.1.0.7 01:23:45:67:89:ab</code>	
<code>ip neigh del 10.1.0.7 dev eth0</code>	Delete a ARP entry
<code>arp -d 10.1.0.7</code>	
<code>ip neigh flush all</code>	Delete the ARP table for all interfaces
<code>iwlist wlan0 scan</code>	List all wireless devices in range, with their quality of signal and other information
<code>iwlist wlan0 freq</code>	Display transmission frequency settings
<code>iwlist wlan0 rate</code>	Display transmission speed settings
<code>iwlist wlan0 txpower</code>	Display transmission power settings
<code>iwlist wlan0 key</code>	Display encryption settings
<code>iwgetid wlan0 option</code>	Print NWID, ESSID, AP/Cell address or other information about the wireless network that is currently in use
<code>iwconfig wlan0</code>	Display configuration of wireless interface wlan0
<code>iwconfig wlan0 option</code>	Configure wireless interface wlan0
<code>hostname</code>	Get the hostname (stored in <code>/etc/hostname</code> )
<code>hostname -f</code>	Get the FQDN (Fully Qualified Domain Name)
<code>hostname mylinuxbox</code>	Set the hostname
<code>hostnamectl set-hostname --static "mylinuxbox" (Red Hat)</code>	
<code>/etc/init.d/networking</code>	Initialize network services
<code>/etc/init.d/network</code>	

<code>dig example.org</code>	Perform a DNS lookup for the specified domain or hostname. Returns information in BIND zone file syntax; uses an internal resolver and hence does not honor <code>/etc/resolv.conf</code>
<code>dig @10.7.7.7 -t MX example.org</code>	Perform a DNS lookup for the MX record of the domain example.org, querying nameserver 10.7.7.7
<code>dig -x 203.0.113.1</code>	Perform a reverse DNS lookup for the IP address 203.0.113.1
<code>host example.org</code>	Perform a DNS lookup for the specified domain or hostname. Does honor <code>/etc/resolv.conf</code>
<code>host example.org 10.7.7.7</code>	Perform a DNS lookup for the domain example.org, querying nameserver 10.7.7.7
<code>host 192.168.13.13</code>	Perform a reverse DNS lookup for the IP address 192.168.13.13
<code>nslookup example.org (deprecated)</code>	Perform a DNS lookup for the specified domain or hostname
<code>whois example.org</code>	Query the WHOIS service for an Internet resource, usually a domain name
<code>ping 10.0.0.2</code>	Test if a remote host can be reached and measure the round-trip time to it (by sending an ICMP ECHO_REQUEST datagram and expecting an ICMP ECHO_RESPONSE)
<code>fping -a 10.0.0.2 10.0.0.7 10.0.0.8</code>	Ping multiple hosts in parallel and report which ones are alive
<code>traceroute 10.0.0.3</code>	Print the route, hop by hop, packets trace to a remote host (by sending a sequence of ICMP ECHO_REQUEST datagrams with increasing TTL values, starting with TTL=1)
<code>tracpath 10.0.0.3</code>	Simpler <code>traceroute</code>
<code>mtr 10.0.0.3</code>	<code>traceroute</code> and <code>ping</code> combined
<code>telnet 10.0.0.4 23</code>	Establish a telnet connection to the specified host and port (if port is omitted, use default port 23)
<code>ftp 10.0.0.5</code>	Establish an interactive FTP connection with host 10.0.0.5
<code>wget --no-clobber --html-extension \</code> <code>--page-requisites --convert-links \</code> <code>--recursive --domains example.org \</code> <code>--no-parent www.example.org/foobar</code>	Download a whole website <code>www.example.org/foobar</code>
<code>nc</code> <code>netcat (SUSE)</code>	Netcat, the Swiss Army knife of networking, a very flexible generic TCP/IP client/server
<code>nc -l -p 25</code>	Listen for connections on port 25 (i.e. mimic a SMTP server). Send any input on stdin to the connected client and dump on stdout any data received from the client
<code>nc 10.0.0.7 389 &lt; myfile</code>	Push the content of a file to port 389 on remote host 10.0.0.7
<code>echo "GET / HTTP/1.0\r\n\r\n"   nc 10.0.0.7 80</code>	Connect to web server 10.0.0.7 and issue a HTTP GET command
<code>while true; \</code> <code>do nc -l -p 80 -q 1 &lt; mypage.html; done</code>	Start a web server, serving the specified HTML page to any connected client
<code>nc -z 10.0.0.7 22</code>	Scan for a listening SSH daemon on remote host 10.0.0.7
<code>nc -v -n -z -w1 -r 10.0.0.7 1-1023</code>	Run a TCP port scan against remote host 10.0.0.7. Probe randomly all privileged ports with a 1-second timeout, without resolving service names, and with verbose output
<code>echo ""   nc -v -n -w1 10.0.0.7 1-1023</code>	Retrieve the greeting banner of any network service that might be running on remote host 10.0.0.7

<code>netstat</code>	Display network connections
<code>netstat --tcp</code> <code>netstat -t</code>	Display active TCP connections
<code>netstat -l</code>	Display only listening sockets
<code>netstat -a</code>	Display all listening and non-listening sockets
<code>netstat -n</code>	Display network connections, without resolving hostnames or portnames
<code>netstat -p</code>	Display network connections, with PID and name of program to which each socket belongs
<code>netstat -i</code>	Display network interfaces
<code>netstat -s</code>	Display protocol statistics
<code>netstat -r</code>	Display kernel routing tables (equivalent to <code>route -e</code> )
<code>netstat -c</code>	Display network connections continuously
<code>ss</code>	Display socket statistics (similar to <code>netstat</code> )
<code>ss -t -a</code>	Display all TCP sockets
<code>nmap 10.0.0.1</code> <code>nmap -sS 10.0.0.1</code>	Scan for open ports (TCP SYN scan) on remote host 10.0.0.1
<code>nmap -sP 10.0.0.1</code>	Do a ping sweep (ICMP ECHO probes) on remote host
<code>nmap -sU 10.0.0.1</code>	Scan UDP ports on remote host
<code>nmap -sV 10.0.0.1</code>	Do a service and version scan on open ports
<code>nmap -p 1-65535 10.0.0.1</code>	Scan all ports (1-65535) on remote host, not only the common ports
<code>nmap -O 10.0.0.1</code>	Find which operating system is running on remote host (OS fingerprinting)
<code>tcpdump -ni eth0</code>	Sniff all network traffic on interface eth0, suppressing DNS resolution
<code>tcpdump ip host 10.0.0.2 tcp port 25</code>	Sniff network packets on TCP port 25 from and to 10.0.0.2
<code>tcpdump ether host '45:67:89:ab:cd:ef'</code>	Sniff traffic from and to the network interface with that MAC address
<code>tcpdump 'src host 10.0.0.2 and \</code> <code>(tcp port 80 or tcp port 443)'</code>	Sniff HTTP and HTTPS traffic having as source host 10.0.0.2
<code>tcpdump -ni eth0 not port 22</code>	Sniff all traffic on eth0 except that belonging to the SSH connection
<code>tcpdump -vvn -i eth0 arp</code>	Sniff ARP traffic on eth0, on maximum verbosity level, without converting host IP addresses and port numbers to names
<code>tcpdump ip host 10.0.0.2 and \</code> <code>not 10.0.0.9</code>	Sniff IP traffic between 10.0.0.2 and any other host except 10.0.0.9
<code>iptraf</code>	IP LAN monitor (ncurses UI)

<code>/sys/class/net</code>	List of all network interfaces in the system
<code>/etc/services</code>	List of service TCP/UDP port numbers
<code>/etc/protocols</code>	List of available protocols
<code>/etc/ethers</code>	ARP mappings (MAC to IP addresses)
<code>/etc/inetd.conf</code>	Configuration file for inetd, the super-server Internet daemon

<code>/etc/hosts</code>	<p>Mappings between IP addresses and hostnames, for name resolution</p> <pre>127.0.0.1    localhost.localdomain  localhost 10.2.3.4     myhost.domain.org   myhost</pre>
<code>/etc/nsswitch.conf</code>	<p>Sources that must be used by various system library lookup functions</p> <pre>passwd:  files nisplus nis shadow:  files nisplus nis group:   files nisplus nis hosts:   files dns nisplus nis</pre>
<code>/etc/host.conf</code>	<p>Sources for name resolution, for systems before glibc2. Obsolete, superseded by <code>/etc/nsswitch.conf</code></p> <pre>order hosts,bind multi on</pre>
<code>/etc/resolv.conf</code>	<p>Specification of domain names that must be appended to bare hostnames and of DNS servers that will be used for name resolution</p> <pre>search domain1.org domain2.org nameserver 192.168.3.3 nameserver 192.168.4.4</pre>
<code>/etc/networks</code>	<p>Mappings between network addresses and names</p> <pre>loopback 127.0.0.0 mylan     10.2.3.0</pre>
<code>/etc/network/interfaces</code>	<p>List and configuration of all network interfaces</p>
<code>/etc/hostname</code> <code>/etc/sysconfig/network</code> (Red Hat)	<p>Hostname of the local machine</p>
<code>/etc/sysconfig/network-scripts/ifcfg-eth0</code> (Red Hat)	<p>Configuration file for network interface eth0. This file is read by the <code>ifup</code> and <code>ifdown</code> scripts</p> <pre>DEVICE=eth0 TYPE=Ethernet HWADDR=AA:BB:CC:DD:EE:FF BOOTPROTO=none ONBOOT=yes NM_CONTROLLED=no IPADDR=10.2.3.4 NETMASK=255.255.255.0 GATEWAY=10.2.3.254 DNS1=8.8.8.8 DNS2=4.4.4.4 USERCTL=no</pre>
<code>/etc/sysconfig/network-scripts/ifcfg-eth0:0</code> (Red Hat) <code>/etc/sysconfig/network-scripts/ifcfg-eth0:1</code> <code>/etc/sysconfig/network-scripts/ifcfg-eth0:2</code>	<p>Configuration files for different interface aliases. This makes possible to bind multiple IP addresses to a single NIC</p>
<code>/etc/sysconfig/network-scripts/route-eth0</code> (Red Hat)	<p>Static route configuration for eth0</p> <pre>ADDRESS=10.2.3.4 NETMASK=255.255.255.0 GATEWAY=10.2.3.254</pre>

/etc/hosts.allow  
/etc/hosts.deny

Host access control files used by the TCP Wrapper system.

Each file contains zero or more *daemon:client* lines. The first matching line is considered.

Access is granted when a *daemon:client* pair matches an entry in /etc/hosts.allow.  
Otherwise, access is denied when a *daemon:client* pair matches an entry in /etc/hosts.deny.  
Otherwise, access is granted.

/etc/hosts.allow and /etc/hosts.deny lines syntax	
ALL: ALL	All services to all hosts
ALL: .example.edu	All services to all hosts of the example.edu domain
ALL: .example.edu EXCEPT host1.example.edu	All services to all hosts of example.edu, except host1
in.fingerd: .example.com	Finger service to all hosts of example.com
in.tftpd: LOCAL	TFTP to hosts of the local domain only
sshd: 10.0.0.3 10.0.0.4 10.1.1.0/24	SSH to the hosts and network specified
sshd: 10.0.1.0/24	SSH to 10.0.1.0/24
sshd: 10.0.1.	SSH to 10.0.1.0/24
sshd: 10.0.1.0/255.255.255.0	SSH to 10.0.1.0/24
in.tftpd: ALL: spawn (/safe_dir/safe_finger \ -l @%h   /bin/mail -s %d-%h root) &	Send a finger probe to hosts attempting TFTP and notify root user via email
portmap: ALL: (echo Illegal RPC request \ from %h   /bin/mail root) &	When a client attempts a RPC request via the portmapper (NFS access), echo a message to the terminal and notify root user via email

route -en		
Kernel IP routing table		
Destination	Gateway	Genmask
192.168.3.0	0.0.0.0	255.255.255.0
0.0.0.0	192.168.3.1	0.0.0.0
Flags	Metric	Ref
U	0	0
UG	0	0
Use	Iface	
0	eth0	
0	eth0	

<b>Gateway</b>	<i>host</i>	gateway name
	*	no gateway
	-	rejected route
<b>Flags</b>	U	route is up
	G	use gateway
	H	target is host
	!	rejected route
	D	dynamically installed by daemon
	M	modified from routing daemon
	R	reinstate route for dynamic routing

```
ip route
route -en
route -F
netstat -rn
```

Display IP routing table

```
ip route show cache
route -C
```

Display kernel routing cache

```
ip route add default via 10.1.1.254
route add default gw 10.1.1.254

ip route add 10.2.0.1 dev eth0
ip route add 10.2.0.1 via 10.2.0.254
route add -host 10.2.0.1 gw 10.2.0.254

ip route add 10.2.0.0/16 via 10.2.0.254
route add -net 10.2.0.0 netmask 255.255.0.0 gw 10.2.0.254

ip route delete 10.2.0.1 dev eth0
route del -host 10.2.0.1 gw 10.2.0.254

ip route flush all
```

Add a default gateway

Add a route for a host

Add a route for a network

Delete a route for a host

Delete the routing table for all interfaces

The Netfilter framework provides firewalling capabilities in Linux. It is implemented by the user-space application programs `iptables` for IPv4 (which replaced `ipchains`, which itself replaced `ipfwadm`) and `ip6tables` for IPv6. In Red Hat the `iptables` service is provided by the `firewalld` daemon.

Tables contain sets of chains, which contain sets of rules.

The filter table contains chains INPUT, FORWARD, OUTPUT (built-in chains).

The NAT table contains chains PREROUTING, OUTPUT, POSTROUTING.

The mangle table contains chains PREROUTING, OUTPUT.

When a packet enters the system, it is handed to the INPUT chain. If the destination is local, it is processed; if the destination is not local and IP forwarding is enabled, the packet is handed to the FORWARD chain, otherwise it is dropped.

An outgoing packet generated by the system will go through the OUTPUT chain.

If NAT is in use, an incoming packet will pass at first through the PREROUTING chain, and an outgoing packet will pass last through the POSTROUTING chain.

<code>iptables -A INPUT -s 10.0.0.6 -j ACCEPT</code>	Add a rule to accept all packets from 10.0.0.6
<code>iptables -A INPUT -s 10.0.0.7 -j REJECT</code>	Add a rule to reject all packets from 10.0.0.7 and send back a ICMP response to the sender
<code>iptables -A INPUT -s 10.0.0.8 -j DROP</code>	Add a rule to silently drop all packets from 10.0.0.8
<code>iptables -A INPUT -s 10.0.0.9 -j LOG</code>	Add a rule to log via Syslog all packets from 10.0.0.9, and take no further action
<code>iptables -D INPUT -s 10.0.0.9 -j LOG</code>	Delete a rule
<code>iptables -D INPUT 42</code>	Delete rule 42 of the INPUT chain
<code>iptables -F INPUT</code>	Flush all rules of the INPUT chain
<code>iptables -t mangle -F</code>	Flush all rules of the mangle table
<code>iptables -t mangle -X</code>	Delete all user-defined (not built-in) rules in the mangle table
<code>iptables -L INPUT</code>	List the rules of the INPUT chain
<code>iptables -P INPUT -j DROP</code>	Define the chain policy, which takes effect when no rule matches and the end of the rules list is reached
<code>iptables -A OUTPUT -d 10.7.7.0/24 -j DROP</code>	Add a rule to drop all packets with destination 10.7.7.0/24
<code>iptables -A FORWARD -i eth0 -o eth1 -j LOG</code>	Add a rule to log all packets entering the system via eth0 and exiting via eth1
<code>iptables -A INPUT -p 17 -j DROP</code>	Add a rule to drop all incoming UDP traffic (protocol numbers are defined in <code>/etc/protocols</code> )
<code>iptables -A INPUT -p udp -j DROP</code>	
<code>iptables -A INPUT --sport 1024:65535 --dport 53 \ -j ACCEPT</code>	Add a rule to accept all packets coming from any unprivileged port and with destination port 53
<code>iptables -A INPUT -p icmp --icmp-type echo-request \ -m limit --limit 1/s -i eth0 -j ACCEPT</code>	Add a rule to accept incoming pings through eth0 at a maximum rate of 1 ping/second
<code>iptables -A INPUT -m state --state ESTABLISHED \ -j ACCEPT</code>	Load the module for stateful packet filtering, and add a rule to accept all packets that are part of a communication already tracked by the state module
<code>iptables -A INPUT -m state --state NEW -j ACCEPT</code>	Add a rule to accept all packets that are not part of a communication already tracked by the state module
<code>iptables -A INPUT -m state --state RELATED -j ACCEPT</code>	Add a rule to accept all packets that are related (e.g. ICMP responses to TCP or UDP traffic) to a communication already tracked by the state module
<code>iptables -A INPUT -m state --state INVALID -j ACCEPT</code>	Add a rule to accept all packets that do not match any of the states above





### SNAT (Source Network Address Translation)

```
iptables -t nat -A POSTROUTING -s 10.0.0.0/24 -o eth1 \
-j SNAT --to-source 93.184.216.119
```

Map all traffic leaving the LAN to the external IP address 93.184.216.119

```
iptables -t nat -A POSTROUTING -s 10.0.0.0/24 -o eth1 \
-j SNAT --to-source 93.184.216.119:93.184.216.127
```

Map all traffic leaving the LAN to a pool of external IP addresses 93.184.216.119-127

```
iptables -t nat -A POSTROUTING -o eth1 -j MASQUERADE
```

Map all traffic leaving the LAN to the address dynamically assigned to eth1 via DHCP

### DNAT (Destination Network Address Translation)

```
iptables -t nat -A PREROUTING -i eth1 -d 93.184.216.119 \
-j DNAT --to-destination 10.0.0.13
```

Allow the internal host 10.0.0.13 to be publicly reachable via the external address 93.184.216.119

### PAT (Port Address Translation)

```
iptables -t nat -A PREROUTING -i eth1 -d 93.184.216.119 \
-p tcp --dport 80 -j DNAT --to-destination 10.0.0.13:8080
```

Make publicly accessible a webserver that is located in the LAN, by mapping port 8080 of the internal host 10.0.0.13 to port 80 of the external address 93.184.216.119

```
iptables -t nat -A PREROUTING -i eth0 -d ! 10.0.0.0/24 \
-p tcp --dport 80 -j REDIRECT --to-ports 3128
```

Redirect all outbound HTTP traffic originating from the LAN to a proxy running on port 3128 on the Linux box

```
iptables-save > fwrules.saved
```

Save iptables configuration to a file

```
iptables-restore < fwrules.saved
```

Restore a iptables configuration from a file

```
sysctl -w net.ipv4.ip_forward=1
echo 1 > /proc/sys/net/ipv4/ip_forward
```

Enable IP forwarding; necessary to set up a Linux machine as a router. (This command causes other network options to be changed as well)

```
/etc/sysconfig/iptables
```

iptables rules

<code>ssh root@remotehost</code>	Connect to a remote host via SSH (Secure Shell) and login as the superuser
<code>ssh -v root@remotehost</code> <code>ssh -vv root@remotehost</code> <code>ssh -vvv root@remotehost</code>	Connect via SSH, with increasing levels of verbosity
<code>ssh -p 2222 root@remotehost</code>	Login as the superuser to a remote host via SSH using port 2222 instead of standard port 22
<code>ssh root@remotehost /root/mycommand</code>	Execute a command on a remote host
<code>sftp root@remotehost</code>	FTP-like tool for secure file transfer
<code>scp myfile root@remotehost:/tmp/myfile2</code> <code>scp root@remotehost:/tmp/myfile2 myfile</code> <code>scp jdoe@host1:/tmp/myfile root@host2:/root/myfile2</code>	Non-interactive secure file copy. Can transfer files from local to remote, from remote to local, or between two remote hosts
<code>sshpass -p p455w0rd ssh root@remotehost</code>	Connect to a remote host using the specified password
<code>pssh -i -H "host1 host2 host3" /root/mycommand</code>	Execute a command in parallel on a group of remote hosts
<code>ssh-keygen -t rsa -b 2048</code>	Generate interactively a 2048-bit RSA key pair, prompting for a passphrase
<code>ssh-keygen -t dsa</code>	Generate a DSA key pair
<code>ssh-keygen -p -t rsa</code>	Change passphrase of the private key
<code>ssh-keygen -q -t rsa -f /etc/ssh/id_rsa -N '' -C ''</code>	Generate a RSA key with no passphrase (for non-interactive use) and no comment
<code>ssh-keygen -lf /etc/ssh/id_rsa.pub</code>	View key length and fingerprint of a public key
<code>ssh-agent</code>	Start the SSH Agent daemon that caches decrypted private keys in memory; also echoes to the terminal the environment variables that must be set. The cached keys are automatically used by SSH tools <code>ssh</code> , <code>sftp</code> , and <code>scp</code>
<code>eval `ssh-agent`</code>	Show the PID of ssh-agent and set appropriate environment variables
<code>ssh-add ~/.ssh/id_rsa</code>	Add a private key to the ssh-agent cache
<code>ssh-copy-id root@remotehost</code>	Use locally available keys to authorize login (via public key authentication) on a remote host

**SSH port forwarding (aka SSH tunneling)**

```
ssh -L 2525:mail.foo.com:25 user@mail.foo.com
```

Establish a SSH encrypted tunnel from localhost to remote host mail.foo.com, redirecting traffic from local port 2525 to port 25 of remote host mail.foo.com.

Useful if the local firewall blocks outgoing port 25. In this case, port 2525 is used to go out; the application must be configured to connect to localhost on port 2525 (instead of mail.foo.com on port 25)

```
ssh -L 2525:mail.foo.com:25 user@login.foo.com
```

Establish a SSH encrypted tunnel from localhost to remote host login.foo.com.

Remote host login.foo.com will then forward, unencrypted, all data received over the tunnel on port 2525 to remote host mail.foo.com on port 25

**SSH reverse forwarding (aka SSH reverse tunneling)**

```
ssh -R 2222:localhost:22 user@login.foo.com
```

Establish a SSH encrypted reverse tunnel from remote host login.foo.com back to localhost, redirecting traffic sent to port 2222 of remote host login.foo.com back towards local port 22.

Useful if the local firewall blocks incoming connections so remote hosts cannot connect back to local machine. In this case, port 2222 of login.foo.com is opened for listening and connecting back to localhost on port 22; remote host login.foo.com is then able to connect to the local machine on port 2222 (redirected to local port 22)

**SSH as a SOCKS proxy**

```
ssh -D 33333 user@login.foo.com
```

The application supporting SOCKS must be configured to connect to localhost on port 33333. Data is tunneled from localhost to login.foo.com, then unencrypted to destination

**X11 Forwarding**

```
ssh -X user@login.foo.com
```

Enable the local display to execute locally a X application stored on a remote host login.foo.com

**How to enable public key authentication**

1. Set `PubkeyAuthentication yes` in `/etc/ssh/sshd_config` of remote server
2. Append your public key `~/.ssh/id_rsa.pub` to the file `~/.ssh/authorized_keys` on the remote server; this can be done by hand or via the command `ssh-copy-id`

**How to enable host-based authentication amongst a group of trusted hosts**

1. Set `HostbasedAuthentication yes` in `/etc/ssh/sshd_config` on all hosts
2. Create `/etc/ssh/shosts.equiv` on all hosts, and enter in this file all trusted hostnames
3. Connect via SSH manually from your machine on each host so that all hosts' public keys go into `~/.ssh/known_hosts`
4. Copy `~/.ssh/known_hosts` from your machine to `/etc/ssh/ssh_known_hosts` on all hosts

**How to enable SSH Agent**

1. Type `eval `ssh-agent``
2. Type `ssh-add` to add the private key to cache, and enter the key's passphrase

**How to enable X11 Forwarding**

1. On remote host 10.2.2.2, set `X11Forwarding yes` in `/etc/ssh/sshd_config`, and make sure that `xauth` is installed
2. On local host 10.1.1.1, type `ssh -X 10.2.2.2`, then run on remote host the graphical application e.g. `xclock &`

X11 Forwarding can also be enabled via telnet (insecure and obsolete)

1. On remote host 10.2.2.2, type `export DISPLAY=10.1.1.1:0.0`
2. On local host 10.1.1.1, type `xhost +`
3. On local host 10.1.1.1, type `telnet 10.2.2.2`, then run on remote host the graphical application e.g. `xclock &`

## SSH files

/etc/ssh/sshd_config	SSH server daemon configuration file
/etc/ssh/ssh_config	SSH client global configuration file
/etc/ssh/ssh_host_key	Host's private key (should be mode 0600)
/etc/ssh/ssh_host_key.pub	Host's public key
/etc/ssh/shosts.equiv	Names of trusted hosts for host-based authentication
/etc/ssh/ssh_known_hosts	Database of host public keys that were previously accepted as legitimate
~/.ssh/	User's SSH directory (must be mode 0700)
~/.ssh/config	SSH client user configuration file
~/.ssh/id_rsa	User's RSA or DSA private key, as generated by <code>ssh-keygen</code>
~/.ssh/id_dsa	
~/.ssh/id_rsa.pub	User's RSA or DSA public key, as generated by <code>ssh-keygen</code>
~/.ssh/id_dsa.pub	
~/.ssh/known_hosts	Host public keys that were previously accepted as legitimate by the user
~/.ssh/authorized_keys	Trusted public keys; the corresponding private keys allow the user to authenticate on this host
~/.ssh/authorized_keys2 (obsolete)	

## /etc/ssh/sshd\_config

PermitRootLogin yes	Control superuser login via SSH. Possible values are:
	yes Superuser can login
	no Superuser cannot login
	without-password Superuser cannot login with password
	forced-commands-only Superuser can only run commands in SSH command line
AllowUsers jdoe ksmith	List of users that can/cannot login via SSH, or * for everybody
DenyUsers jhacker	
AllowGroups geeks	List of groups whose members can/cannot login via SSH, or * for all groups
DenyGroups *	
PasswordAuthentication yes	Permit authentication via login and password
PubKeyAuthentication yes	Permit authentication via public key
HostbasedAuthentication yes	Permit authentication based on trusted hosts
Protocol 1,2	Specify protocols supported by SSH. Value can be 1 or 2 or both
X11Forwarding yes	Allow X11 Forwarding

```
gpg --gen-key
gpg --import alice.asc
gpg --list-keys
gpg --list-secret-keys
gpg --list-public-keys
gpg --export -o keyring_backup.gpg
gpg --export-secret-key -a "You" -o private.key
gpg --export-public-key -a "Alice" -o alice.pub
gpg --edit-key "Alice"
gpg -e -u "You" -r "Alice" file.txt

gpg -d file.txt.gpg
```

Generate a key pair

Import Alice's public key into your keyring

List the keys contained into your keyring

List your private keys contained into your keyring

List the public keys contained into your keyring

Export your whole keyring to a file

Export your private key (username You) to a file

Export Alice's public key to a file

Sign Alice's public key

Encrypt a file (to Alice i.e. with Alice's public key),  
signing it with your private key

Decrypt a file (with your own public key)

```
md5sum
sha1sum
sha224sum
sha256sum
sha384sum
sha512sum
```

Print a digest of a file depending on the selected  
hashing algorithm

```
openvpn --genkey --secret keyfile
```

Generate a shared secret keyfile for OpenVPN authentication.  
The keyfile must be copied on both server and client

```
openvpn server.conf
```

Start the VPN on the server side. The encrypted VPN tunnel uses UDP port 1194

```
openvpn client.conf
```

Start the VPN on the client side

```
/etc/openvpn/server.conf
```

Server-side configuration file:

```
dev tun
ifconfig [server IP] [client IP]
keepalive 10 60
ping-timer-rem
persist-tun
persist-key
secret keyfile
```

```
/etc/openvpn/client.conf
```

Client-side configuration file:

```
remote [server public IP]
dev tun
ifconfig [client IP] [server IP]
keepalive 10 60
ping-timer-rem
persist-tun
persist-key
secret keyfile
```

Key	Alternate key	Function
<b>CTRL</b> <b>F</b>	<b>→</b>	Move cursor forward one char
<b>CTRL</b> <b>B</b>	<b>←</b>	Move cursor backward one char
<b>CTRL</b> <b>A</b>	<b>HOME</b>	Move cursor to beginning of line
<b>CTRL</b> <b>E</b>	<b>END</b>	Move cursor to end of line
<b>CTRL</b> <b>H</b>	<b>BACKSPACE</b>	Delete char to the left of cursor
<b>CTRL</b> <b>W</b>		Delete word to the left of cursor
<b>CTRL</b> <b>U</b>		Delete all chars to the left of cursor
<b>CTRL</b> <b>K</b>		Delete all chars to the right of cursor
<b>CTRL</b> <b>T</b>		Swap current char with previous char
<b>ESC</b> <b>T</b>		Swap current word with previous word
<b>SHIFT</b> <b>PAGE UP</b>		Scroll up the buffer
<b>SHIFT</b> <b>PAGE DOWN</b>		Scroll down the buffer
<b>CTRL</b> <b>L</b>		Clear screen (same as <code>clear</code> )
<b>CTRL</b> <b>P</b>	<b>↑</b>	Previous command in history
<b>CTRL</b> <b>N</b>	<b>↓</b>	Next command in history
<b>CTRL</b> <b>R</b>		Reverse history search
<b>TAB</b>		Autocomplete file and directory names
<b>CTRL</b> <b>J</b>	<b>RETURN</b>	Line feed
<b>CTRL</b> <b>M</b>		Carriage return
<b>CTRL</b> <b>S</b>		Pause trasfer to terminal
<b>CTRL</b> <b>Q</b>		Resume transfer to terminal
<b>CTRL</b> <b>Z</b>		Send a SIGTSTP to put the current job in background
<b>CTRL</b> <b>C</b>		Send a SIGINT to stop the current process
<b>CTRL</b> <b>D</b>		Send a EOF to current process (same as <code>logout</code> )
<b>CTRL</b> <b>ALT</b> <b>DEL</b>		Send a SIGINT to reboot the machine (same as <code>shutdown -r now</code> ), as specified in <code>/etc/inittab</code> and <code>/etc/init/control-alt-delete</code>
<b>CTRL</b> <b>ALT</b> <b>F1 ... F6</b>		Switch between text consoles
<b>CTRL</b> <b>ALT</b> <b>F7 ... F11</b>		Switch between X Window consoles
<b>CTRL</b> <b>ALT</b> <b>+</b>		Increase X Window screen resolution
<b>CTRL</b> <b>ALT</b> <b>-</b>		Decrease X Window screen resolution
<b>CTRL</b> <b>TAB</b>		Switch between X Window tasks
<b>CTRL</b> <b>ALT</b> <b>→</b>		Switch to next workspace
<b>CTRL</b> <b>ALT</b> <b>←</b>		Switch to previous workspace
<b>CTRL</b> <b>ALT</b> <b>BACKSPACE</b>		Reboot the X Window server

The Hardware Abstraction Layer (HAL) manages device files and provides plug-and-play facilities. The HAL daemon `hald` maintains a persistent database of devices.

`udev` dynamically generates the device nodes in `/dev/` for devices present on the system. `udev` also provides persistent naming for storage devices in `/dev/disk`.

When a device is added, removed, or changes state, the kernel sends an `uevent` received by the `udev` daemon which will pass the `uevent` through a set of rules stored in `/etc/udev/rules.d/*.rules` and `/lib/udev/rules.d/*.rules`.

<code>udevadm monitor</code> <code>udevmonitor</code>	Show all kernel <code>uevents</code> and <code>udev</code> messages
<code>udevadm info --attribute-walk --name=/dev/sda</code>	Print all attributes of device <code>/dev/sda</code> in <code>udev</code> rules key format
<code>cat /sys/block/sda/size</code>	Print the size attribute of disk <code>sda</code> in 512-byte blocks. This information is retrieved from <code>sysfs</code>
<code>udevadm test /dev/sdb</code>	Simulate a <code>udev</code> event run for the device and print debug output
<code>gnome-device-manager</code>	Browser for the HAL device manager

<code>/etc/udev/rules.d/*.rules</code> and <code>/lib/udev/rules.d/*.rules</code>	<code>udev</code> rules
<code>KERNEL=="hda", NAME="mydisk"</code>	Match a device which was named by the kernel as <code>hda</code> ; name the device node as <code>mydisk</code> . The device node will be therefore <code>/dev/mydisk</code>
<code>KERNEL=="hdb", DRIVER=="ide-disk", SYMLINK+="mydisk myhd"</code>	Match a device with kernel name and driver as specified; name the device node with the default name and create two symbolic links <code>/dev/mydisk</code> and <code>/dev/myhd</code> pointing to <code>/dev/hdb</code>
<code>KERNEL=="fd[0-9]*", NAME="floppy/%n", SYMLINK+="%k"</code>	Match all floppy disk drives (i.e. <code>fdn</code> ); place device node in <code>/dev/floppy/n</code> and create a symlink <code>/dev/fdn</code> to it
<code>SUBSYSTEM=="block", ATTR{size}=="41943040", SYMLINK+="mydisk"</code>	Match a block device with a size attribute of 41943040; create a symlink <code>/dev/mydisk</code>
<code>KERNEL=="fd[0-9]*", OWNER="jdoe"</code>	Match all floppy disk drives; give ownership of the device file to user <code>jdoe</code>
<code>KERNEL=="sda", PROGRAM="/bin/mydevicenamer %k", SYMLINK+="%c"</code>	Match a device named by the kernel as <code>sda</code> ; to name the device, use the defined program which takes on stdin the kernel name and output on stdout e.g. <code>name1 name2</code> . Create symlinks <code>/dev/name1</code> and <code>/dev/name2</code> pointing to <code>/dev/sda</code>
<code>KERNEL=="sda", ACTION=="add", RUN+="/bin/myprogram"</code>	Match a device named by the kernel as <code>sda</code> ; run the defined program when the device is connected
<code>KERNEL=="sda", ACTION=="remove", RUN+="/bin/myprogram"</code>	Match a device named by the kernel as <code>sda</code> ; run the defined program when the device is disconnected
%n = kernel number (e.g. = 3 for <code>fd3</code> ) %k = kernel name (e.g. = <code>fd3</code> for <code>fd3</code> ) %c = device name as output from program	



A kernel version number has the form *major.minor.patchlevel*.

Kernel images are usually gzip-compressed and can be of two types: zImage (max 520 Kb) and bzImage (no size limit). Kernel modules can be loaded dynamically into the kernel to provide additional functionalities on demand, instead of being included when the kernel is compiled; this reduces memory footprint.

`kernel` (daemon) and `kmod` (kernel thread) facilitate the dynamic loading of kernel modules.

<code>/lib/modules/X.Y.Z/*.ko</code>	Kernel modules for kernel version X.Y.Z
<code>/lib/modules/X.Y.Z/modules.dep</code>	Modules dependencies. This file needs to be recreated (via the command <code>depmod -a</code> ) after a reboot or a change in module dependencies
<code>/etc/modules.conf</code> <code>/etc/conf.modules</code> (deprecated)	Modules configuration file
<code>/usr/src/linux/</code> <code>/usr/src/linux/.config</code>	Contains the kernel source code to be compiled Kernel configuration file
<code>freeramdisk</code>	Free the memory used for the <code>initrd</code> image. This command must be run directly after unmounting <code>/initrd</code>
<code>mkinitrd [initrd image] [kernel version]</code>	Create a <code>initrd</code> image file (Red Hat)
<code>mkinitramfs</code>	Create a <code>initrd</code> image file according to the configuration file <code>/etc/initramfs-tools/initramfs.conf</code> (Debian)
<code>dracut</code>	Create initial ramdisk images for preloading modules
<code>dbus-monitor</code>	Monitor messages going through a D-Bus message bus
<code>dbus-monitor --session</code>	Monitor session messages (default)
<code>dbus-monitor --system</code>	Monitor system messages

The runtime loader `ld.so` loads the required shared libraries of the program into RAM, searching in this order:

1. `LD_LIBRARY_PATH` Environment variable specifying the list of dirs where libraries should be searched for first
2. `/etc/ld.so.cache` Cache file
3. `/lib` and `/usr/lib` Default locations for shared libraries

<code>/etc/ld.so.conf</code>	Configuration file used to specify other shared library locations (other than the default ones <code>/lib</code> and <code>/usr/lib</code> )
<code>ldconfig</code>	Create a cache file <code>/etc/ld.so.cache</code> of all available dynamically linked libraries. To be run when the system complains about missing libraries
<code>ldd [program or lib]</code>	Print library dependencies

<code>lsdev</code>	List information about the system's hardware
<code>lspci</code>	List PCI devices
<code>lspci -d 8086:</code>	List all Intel hardware present. PCI IDs are stored in <code>/usr/share/misc/pci.ids</code> (Debian) or <code>/usr/share/hwdata/pci.ids</code> (Red Hat)
<code>lsusb</code>	List USB devices
<code>lsusb -d 8086:</code>	List all Intel USB devices present. USB IDs are stored in <code>/var/lib/usbutils/usb.ids</code>
<code>lshw</code>	List system hardware
<code>dmesg</code>	Print the messages of the kernel ring buffer
<code>dmesg -n 1</code>	Set the logging level to 1 (= only panic messages)
<code>journalctl</code>	Query the systemd journal
<code>journalctl -xn</code>	Query the systemd journal for recent events only, and adding explanation texts
<code>journalctl -f</code>	Query the systemd journal in real time, scrolling as new entries are added
<code>uname -s</code>	Print the kernel name
<code>uname -n</code>	Print the network node hostname
<code>uname -r</code>	Print the kernel release number <code>X.Y.Z</code>
<code>uname -v</code>	Print the kernel version number
<code>uname -m</code>	Print the machine hardware name
<code>uname -p</code>	Print the processor type
<code>uname -i</code>	Print the hardware platform
<code>uname -o</code>	Print the operating system
<code>uname -a</code>	Print all the above information, in that order

Kernel compile		
<b>Download</b>	Download kernel source code <code>linux-X.Y.Z.tar.bz2</code> from <a href="http://www.kernel.org">http://www.kernel.org</a> to the base of the kernel source tree <code>/usr/src/linux</code>	
<b>Clean</b>	<code>make clean</code>	Delete most generated files
	<code>make mrproper</code>	Delete all generated files and kernel configuration
	<code>make distclean</code>	Delete temporary files, patch leftover files, and similar
<b>Configure</b>	<code>make config</code>	Terminal-based (options must be set in sequence)
	<code>make menuconfig</code>	ncurses UI
	<code>make xconfig</code> <code>make gconfig</code>	GUI
	<code>make oldconfig</code>	Create a new config file, based on the options in the old config file and in the source code
	Components (e.g. device drivers) can be either: <ul style="list-style-type: none"> <li>- not compiled</li> <li>- compiled into the kernel binary, for support of devices always used on the system or necessary for the system to boot</li> <li>- compiled as a kernel module, for optional devices</li> </ul>	
	The configuration command creates a <code>/usr/src/linux/.config</code> config file containing instructions for the compile	
<b>Build</b>	<code>make bzImage</code>	Compile the kernel
	<code>make modules</code>	Compile the kernel modules
	<code>make all</code>	Compile kernel and kernel modules
	<code>make -j2 all</code> will speed up compilation by allocating 2 simultaneous compile jobs	
<b>Modules install</b>	<code>make modules_install</code>	Install the previously built modules present in <code>/lib/modules/X.Y.Z</code>
<b>Kernel install</b>	<code>make install</code>	Install the kernel automatically
	To install the kernel by hand: Copy the new compiled kernel and other files into the boot partition <code>cp /usr/src/linux/arch/boot/bzImage /boot/vmlinuz-X.Y.Z</code> (kernel) <code>cp /usr/src/linux/arch/boot/System.map-X.Y.Z /boot</code> <code>cp /usr/src/linux/arch/boot/config-X.Y.Z /boot</code> (config options used for this compile) Create an entry in GRUB to boot on the new kernel	
	Optionally, the kernel can be packaged for install on other machines	
<b>Package</b>	<code>make rpm-pkg</code>	Build source and binary RPM packages
	<code>make binrpm-pkg</code>	Build binary RPM package
	<code>make deb-pkg</code>	Builds binary DEB package

Kernel patching		
<b>Download</b>	Download and decompress the patch to <code>/usr/src</code>	
<b>Patch</b>	<code>patch -p1 &lt; file.patch</code>	Apply the patch
	<code>patch -Rp1 &lt; file.patch</code>	To remove a patch, you can either apply the patch again or use this command (reverse patch)
<b>Build</b>	Build the patched kernel as explained previously	
<b>Install</b>	Install the patched kernel as explained previously	

Kernel modules allow the kernel to access functions (symbols) for kernel services e.g. hardware drivers, network stack, or filesystem abstraction.

<code>lsmod</code>	List the modules that are currently loaded into the kernel
<code>insmod module</code>	Insert a module into the kernel. If the module requires another module or if it does not detect compatible hardware, insertion will fail
<code>rmmod module</code>	Remove a module from the kernel. If the module is in use by another module, it is necessary to remove the latter first
<code>modinfo module</code>	Display the list of parameters accepted by the module
<code>depmod -a</code>	Probe all modules in the kernel modules directory and generate the file that lists their dependencies

It is recommended to use `modprobe` instead of `insmod/rmmod`, because it automatically handles prerequisites when inserting modules, is more specific about errors, and accepts just the module name instead of requiring the full pathname.

<code>modprobe module option=value</code>	Insert a module into the running kernel, with the specified parameters. Prerequisite modules will be inserted automatically
<code>modprobe -a</code>	Insert all modules
<code>modprobe -t directory</code>	Attempt to load all modules contained in the directory until a module succeeds. This action probes the hardware by successive module-insertion attempts for a single type of hardware, e.g. a network adapter
<code>modprobe -r module</code>	Remove a module
<code>modprobe -c module</code>	Display module configuration
<code>modprobe -l</code>	List loaded modules

Configuration of device drivers					
Device drivers support the kernel with instructions on how to use that device.					
<b>Device driver compiled into the kernel</b>	Configure the device driver by passing a kernel parameter in the GRUB menu: <code>kernel /vmlinuz ro root=/dev/vg0/root vga=0x33c</code>				
<b>Device driver provided as a kernel module</b>	Edit module configuration in <code>/etc/modprobe.conf</code> or <code>/etc/modprobe.d/</code> (Red Hat): <table> <tr> <td><code>alias eth0 3c59x</code></td><td>Specify that eth0 uses the 3c59x.ko driver module</td></tr> <tr> <td><code>options 3c509 irq=10,11</code></td><td>Assign IRQ 10 and 11 to 3c509 devices</td></tr> </table>	<code>alias eth0 3c59x</code>	Specify that eth0 uses the 3c59x.ko driver module	<code>options 3c509 irq=10,11</code>	Assign IRQ 10 and 11 to 3c509 devices
<code>alias eth0 3c59x</code>	Specify that eth0 uses the 3c59x.ko driver module				
<code>options 3c509 irq=10,11</code>	Assign IRQ 10 and 11 to 3c509 devices				

/proc pseudo filesystem		
File	Information stored	Equivalent command to cat
/proc/n/	Information about process with PID <i>n</i>	ps <i>n</i>
/proc/n/cmdline	Command line the process was launched by	
/proc/n/envIRON	Values of environment variables of process	
/proc/n/status	Status of process	
/proc/n/root	Symlink to process' filesystem root	
/proc/n/exe	Symlink to process' executable	
/proc/n/cwd	Symlink to process' working directory	
/proc/sys/	sysfs: exposes tunable kernel parameters	
/proc/sys/kernel/	Kernel information and parameters	
/proc/sys/net/	Network information and parameters	
/proc/uptime	Time elapsed since boot	uptime
/proc/loadavg	System load averages	uptime
/proc/filesystems	Filesystems supported by the system	
/proc/partitions	Drive partition information	
/proc/mdstat	Information about RAID arrays and devices	
/proc/swaps	Size of total and used swap areas	swapon -s
/proc/mounts	Mounted partitions	mount
/proc/devices	Drivers currently loaded	
/proc/modules	Kernel modules currently loaded	lsmod
/proc/bus	Buses (e.g. PCI, USB, PC Card)	
/proc/ioports	I/O addresses in use	
/proc/dma	DMA channels in use	
/proc/interrupts	Current IRQs (Interrupt Requests)	procinfo
/proc/cpuinfo	CPUs information	
/proc/meminfo	Total and free memory	free
/proc/version	Linux version	uname -a

/proc/sys is the only writable branch of /proc and can be used to tune kernel parameters on-the-fly. All changes will be lost after system shutdown.

```
sysctl fs.file-max
cat /proc/sys/fs/file-max
```

Get the maximum allowed number of open files

```
sysctl -w "fs.file-max=100000"
echo "100000" > /proc/sys/fs/file-max
```

Set the maximum allowed number of open files to 100000

```
sysctl -a
sysctl -p
```

List all available kernel tuning options

Apply all tuning settings listed in /etc/sysctl.conf .  
This command is usually run at boot by the system initialization script and therefore allows for permanent changes to the kernel

If the kernel has been booted in emergency mode and `init` has not been run, some initial configuration is necessary e.g.

```
mount /proc
mount -o remount,rw /
mount -a
```

If mounting filesystems fails:

```
mknod /dev/sda
mknod /dev/sda1
fdisk -l /dev/sda
fsck -y /dev/sda1
mount -t ext3 /dev/sda1 /mnt/sysimage
chroot /mnt/sysimage
```

To install a package using an alternative root directory (useful if the system has been booted from a removable media):

```
rpm -U --root /mnt/sysimage package.rpm
```

To install GRUB on the specified directory (which must contain `/boot/grub/`):

```
grub-install --root-directory=/mnt/sysimage /dev/sda
```

An alternative method is to `chroot /mnt/sysimage` before installing GRUB via `grub-install /dev/sda`.

Run `sync` and unmount filesystems before exiting the shell, to ensure that all changes have been written on disk.

DNS implementations	
BIND	Berkeley Internet Name Domain system, is the standard DNS server for UNIX
dnsmasq	Lightweight DNS, DHCP and TFTP server for a small network
djbdns	Security-hardened DNS server that also includes DNS debugging tools
PowerDNS	Alternative open-source DNS server

**named** BIND Name Daemon  
**ndc** Name Daemon Controller for BIND 8  
**rndc** Remote Name Daemon Controller for BIND 9, uses a shared key to communicate securely with **named**

**dnswalk example.org.** DNS debugger

**rndc reconfig** Reload BIND configuration and new zones  
**rndc reload example.org** Reload the zone example.org  
**rndc freeze example.org** Suspend updates for the zone example.org  
**rndc thaw example.org** Resume updates for the zone example.org  
**rndc tsig-list** List all currently active TSIG keys

DNSSEC was designed to secure the DNS tree and hence prevent cache poisoning. The TSIG (Transaction SIGNature) standard, that authenticates communications between two trusted systems, is used to sign zone transfers and DDNS (Dynamic DNS) updates.

**dnssec-keygen -a dsa -b 1024 \**  
**-n HOST dns1.example.org**

Generate a TSIG key with DNSSEC algorithm *nnn* and key fingerprint *fffff*. This will create two key files  
 Kdns1.example.org.+nnn+fffff.key  
 Kdns1.example.org.+nnn+fffff.private  
 which contain a key number that has to be inserted both in `/etc/named.conf` and `/etc/rndc.conf`

**rndc-confgen -a**

Generate a `/etc/rndc.key` key file:

```
key "rndc-key" {
    algorithm hmac-md5;
    secret "vyZqL3tPHsqnA57e4LT0Ek==";
};
options {
    default-key "rndc-key";
    default-server 127.0.0.1;
    default-port 953;
};
```

This file is automatically read both by **named** and **rndc**

**dnssec-signzone example.org** Sign the zone example.org

**named -u named -g named** Run BIND as user/group named (both must be created if needed) instead of root  
**named -t /var/cache/bind** Run BIND in a chroot jail `/var/cache/bind` (actually is the `chroot` command that starts the **named** server)

**/etc/named.conf    DNS server configuration file**

```

controls {
    inet 127.0.0.1 allow {localhost;} keys {rndckey};
};
key "rndc-key" {
    algorithm dsa;
    secret "HYZur46fftdUQ43BJKI093t4t781kp";
};

acl "mynetwork" {10.7.0.0/24;};

options {
    directory "/var/named";
    version "0.0";
    listen-on port 53 {10.7.0.1; 127.0.0.1;};
    blackhole {172.17.17.0/24;};
    allow-query {mynetwork;};
    allow-query-on {any;};
    allow-query-cache {any;};
    allow-recursion {mynetwork;};

    allow-recursion-on {mynetwork;};
    allow-transfer {10.7.0.254;};

    allow-update {any;};
    recursive-clients 1000;
    dnssec-enable yes;
    dialup no;

    forward first;
    forwarders {10.7.0.252; 10.7.0.253;};

};

// Define the root name servers
zone "." {
    type hint;
    file "root.cache";
}

// Configure system to act as a master server for the example.org domain
zone "example.org" IN {
    type master;
    file "master/example.org.zone";
};

zone "240.123.224.in-addr.arpa" IN {
    type master;
    file "slave/example.org.revzone";
};

// Configure system to act as a slave server for the example2.org domain
zone "example2.org" IN {
    type slave;
    file "slave/example2.org.zone";
    masters {10.7.0.254;};
};

zone "0.7.10.in-addr.arpa" IN {
    type slave;
    file "slave/10.7.0.revzone";
    masters {10.7.0.254;};
};

```



/var/named/master/example.org.zone		DNS zone file for the example.org zone	
\$TTL	86400		; TTL (1 day)
\$ORIGIN	example.org.		
example.org	IN	SOA	dns1.example.org. help.example.org. ( ; Master DNS server is dns1.example.org 2014052300 ; serial ; For problems contact help@example.org 28800 ; refresh (8 hours) 7200 ; retry (2 hours) 604800 ; expire (1 week) 600 ) ; negative TTL (10 mins)
	IN	NS	dns1.example.org.
	IN	NS	dns2.example.org.
	IN	MX	10 mail1.example.org.
	IN	MX	20 mail2.example.org.
dns1	IN	A	224.123.240.3
dns2	IN	A	224.123.240.4
mail1	IN	A	224.123.240.73
mail2	IN	A	224.123.240.77
foo	IN	A	224.123.240.12
bar	IN	A	224.123.240.13
www	IN	A	224.123.240.19
baz	IN	CNAME	bar
subdomain	IN	NS	ns1.subdomain.example.org. ; Glue records
	IN	NS	ns2.subdomain.example.org.
ns1.subdomain.example.org.	IN	A	224.123.240.201
ns2.subdomain.example.org.	IN	A	224.123.240.202

/var/named/master/example.org.revzone		DNS reverse zone file for the example.org zone	
\$TTL	86400		; TTL (1 day)
example.org	IN	SOA	dns1.example.org. help.example.org. (
	2014052300		; serial
	28800		; refresh (8 hours)
	7200		; retry (2 hours)
	604800		; expire (1 week)
	600		; negative TTL (10 mins)
12.240.123.224.in-addr.arpa	IN	PTR	foo
13.240.123.224.in-addr.arpa	IN	PTR	bar
19.240.123.224.in-addr.arpa	IN	PTR	www

Resource Records	
\$TTL	How long to cache a positive response
\$ORIGIN	Suffix appended to all names not ending with a dot. Useful when defining multiple subdomains inside the same zone
<b>SOA</b>	Start Of Authority for the example.org zone
serial	Serial number. Must be increased after each edit of the zone file
refresh	How frequently a slave server refreshes its copy of zone data from the master
retry	How frequently a slave server retries connecting to the master
expire	How long a slave server relies on its copy of zone data. After this time period expires, the slave server is not authoritative anymore for the zone unless it can contact a master
negative TTL	How long to cache a non-existent answer
<b>A</b>	Address: maps names to IP addresses. Used for DNS lookups.
<b>PTR</b>	Pointer: maps IP addresses to names. Used for reverse DNS lookups. Each A record must have a matching PTR record
<b>CNAME</b>	Canonical Name: specifies an alias for a host with an A record (even in a different zone). Discouraged as it causes multiple lookups; it is better to use multiple A records instead
<b>NS</b>	Name Service: specifies the authoritative name servers for the zone
<b>MX</b>	Mailserver: specifies address and priority of the servers able to handle mail for the zone
Glue Records are not really part of the zone; they delegate authority for other zones, usually subdomains	

Methods of MPM (Multi-Processing Modules) operation of the Apache webserver:

prefork MPM	A number of child processes is spawned in advance, with each child serving exclusively one connection. Highly reliable due to Linux memory protection that isolates each child process
worker MPM	Multiple child processes spawn multiple threads, with each thread serving one connection. More scalable but prone to deadlocks if third-party non-threadsafe modules are loaded

apache2ctl start	Start the Apache webserver daemon httpd
apache2ctl status	Display a brief status report
apache2ctl fullstatus	Display a detailed status report
apache2ctl graceful	Gracefully restart Apache; currently open connections are not aborted
apache2ctl graceful-stop	Gracefully stop Apache; currently open connections are not aborted
apache2ctl configtest	Test the configuration file, reporting any syntax error

/var/www/html	Default document root directory
\$HOME/public_html	Default document root directory for users' websites

Web content must be readable by the user/group the Apache process runs as. For security reasons, it should be owned and writable by the superuser or the webmaster user/group, not the Apache user/group.

/etc/httpd/conf/httpd.conf	(Red Hat)	Apache configuration file
/etc/apache2/httpd.conf	(Debian and SUSE)	

## HTTPS

A secure web server (using HTTP over SSL i.e. HTTPS) hands over its public key to the client when the latter connects to it via port 443. The server's public key is signed by a CA (Certification Authority), whose validity is ensured by the root certificates stored into the client's browser.

The `openssl` command and its user-friendly `CA.pl` script are the tools of the OpenSSL crypto library that can be used to accomplish all public key crypto operations e.g. generate key pairs, Certificate Signing Requests, self-signed certificates.

Virtual hosting with HTTPS requires assigning an unique IP address for each virtual host; this because the SSL handshake (during which the server sends its certificate to the client's browser) takes place before the client sends the `Host:` header (which tells which virtual host the client wants to talk to).

A workaround for this is SNI (Server Name Indication) that makes the browser send the hostname in the first message of the SSL handshake. Another workaround is to have all multiple name-based virtual hosts use the same SSL certificate with a wildcard domain `*.example.org`.

/etc/ssl/openssl.cnf	Configuration file for OpenSSL
/etc/httpd/conf.d/ssl.conf	(Red Hat) Configuration file for the mod_ssl module

httpd.conf															
Server configuration directives															
<pre> ServerName www.mysite.org:80 ServerRoot /etc/httpd ServerAdmin webmaster@mysite.org  StartServers 5 MinSpareServers 5 MaxSpareServers 10  MaxClients 256          (before v2.3.13) MaxRequestWorkers 256   (after v2.3.13)  ServerLimit 256  ThreadsPerChild 25 ThreadLimit 64  LoadModule mime_module modules/mod_mime.so  Listen 10.17.1.1:80 Listen 10.17.1.5:8080  User nobody Group nobody </pre>	<p>Name and port (if omitted, uses default HTTP port 80) of server</p> <p>Root directory for config and log files</p> <p>Contact address that the server includes in any HTTP error messages to the client. Can be an email address or an URL</p> <p>Number of servers to start initially</p> <p>Minimum and maximum number of idle child server processes</p> <p>Max number of simultaneous requests that will be served; clients above this limit will get a HTTP error 503 - Service Unavailable. Prefork MPM: max number of child processes launched to serve requests. Worker MPM: max total number of threads available to serve requests</p> <p>Prefork MPM: max configured value for <code>MaxRequestWorkers</code>. Worker MPM: in conjunction with <code>ThreadLimit</code>, max configured value for <code>MaxRequestWorkers</code></p> <p>Worker MPM: number of threads created by each child process</p> <p>Worker MPM: max configured value for <code>ThreadsPerChild</code></p> <p>Load the module <code>mime_module</code> by linking in the object file or library <code>modules/mod_mime.so</code></p> <p>Make the server accept connections on the specified IP addresses (optional) and ports</p> <p>User and group the Apache process runs as. For security reasons, this should not be <code>root</code></p>														
Main configuration directives															
<pre> DocumentRoot /var/www/html Alias /image /mydir/pub/image  TypesConfig conf/mime.types AddType image/jpeg jpeg jpg jpe  Redirect permanent /foo /bar  Redirect /foo http://www.example.com/foo AccessFileName .htaccess  &lt;Directory "/var/www/html/foobar"&gt;     AllowOverride AuthConfig Limit &lt;/Directory&gt; </pre>	<p>Directory in filesystem that maps to the root of the website</p> <p>Map the URL <code>http://www.mysite.org/image/</code> to the directory <code>/mydir/pub/image</code> in the filesystem. This allows Apache to serve content placed outside of the document root</p> <p>Media types file. The path is relative to <code>ServerRoot</code></p> <p>Map the specified filename extensions onto the specified content type. These entries adds to or override the entries from the media types file <code>conf/mime.types</code></p> <p>Redirect to a URL on the same host. Status can be:  <code>permanent</code> return a HTTP status 301 - Moved Permanently  <code>temp</code> return a HTTP status 302 - Found (i.e. the resource was temporarily moved)  <code>seeother</code> return a HTTP status 303 - See Other  <code>gone</code> return a HTTP status 410 - Gone  If status is omitted, default status <code>temp</code> is used</p> <p>Redirect to a URL on a different host</p> <p>Name of the distributed configuration file, which contains directives that apply to the document directory it is in and to all its subtrees</p> <p>Specify which global directives a <code>.htaccess</code> file can override:</p> <table> <tr><td><code>AuthConfig</code></td><td>authorization directives for directory protection</td></tr> <tr><td><code>FileInfo</code></td><td>document type and metadata</td></tr> <tr><td><code>Indexes</code></td><td>directory indexing</td></tr> <tr><td><code>Limit</code></td><td>host access control</td></tr> <tr><td><code>Options</code></td><td>specific directory features</td></tr> <tr><td><code>All</code></td><td>all directives</td></tr> <tr><td><code>None</code></td><td>no directive</td></tr> </table>	<code>AuthConfig</code>	authorization directives for directory protection	<code>FileInfo</code>	document type and metadata	<code>Indexes</code>	directory indexing	<code>Limit</code>	host access control	<code>Options</code>	specific directory features	<code>All</code>	all directives	<code>None</code>	no directive
<code>AuthConfig</code>	authorization directives for directory protection														
<code>FileInfo</code>	document type and metadata														
<code>Indexes</code>	directory indexing														
<code>Limit</code>	host access control														
<code>Options</code>	specific directory features														
<code>All</code>	all directives														
<code>None</code>	no directive														

httpd.conf	
Virtual hosts directives	
<pre>NameVirtualHost *</pre>	Specify which IP address will serve virtual hosting. The argument can be an IP address, an <i>address:port</i> pair, or * for all IP addresses of the server. The argument will be repeated in the relevant <code>&lt;VirtualHost&gt;</code> directive
<pre>&lt;VirtualHost *:80&gt;   ServerName www.mysite.org   ServerAlias mysite.org *.mysite.org   DocumentRoot /var/www/vhosts/mysite &lt;/VirtualHost&gt;</pre>	<p>The first listed virtual host is also the default virtual host. It inherits those main settings that does not override. This virtual host answers to <code>http://www.mysite.org</code>, and also redirects there all HTTP requests on the domain <code>mysite.org</code></p>
<pre>&lt;VirtualHost *:80&gt;   ServerAdmin webmaster@www.mysite2.org   ServerName www.mysite2.org   DocumentRoot /var/www/vhosts/mysite2   ErrorLog /var/www/logs/mysite2 &lt;/VirtualHost&gt;</pre>	<p>Name-based virtual host <code>http://www.mysite2.org</code>. Multiple name-based virtual hosts can share the same IP address; DNS must be configured accordingly to map each name to the correct IP address. Cannot be used with HTTPS</p>
<pre>&lt;VirtualHost *:8080&gt;   ServerName www.mysite3.org   DocumentRoot /var/www/vhosts/mysite3 &lt;/VirtualHost&gt;</pre>	<p>Port-based virtual host answering to connections on port 8080. In this case the config file must contain a <code>Listen 8080</code> directive</p>
<pre>&lt;VirtualHost 10.17.1.5:80&gt;   ServerName www.mysite4.org   DocumentRoot /var/www/vhosts/mysite4 &lt;/VirtualHost&gt;</pre>	<p>IP-based virtual host answering to <code>http://10.17.1.5</code></p>
Logging directives	
<pre>LogFormat "%h %l %u %t \"%r\" %&gt;s %b"</pre>	Specify the format of a log
<pre>LogFormat "%h %l %u %t \"%r\" %&gt;s %b" common</pre>	<p>Specify a nickname (here, "common") for a log format. This one is the CLF (Common Log Format) defined as such:</p> <ul style="list-style-type: none"> <li>%h IP address of the client host</li> <li>%l Identity of client as determined by <code>identd</code></li> <li>%u User ID of client making the request</li> <li>%t Timestamp the server completed the request</li> <li>%r Request as done by the user</li> <li>%s Status code sent by the server to the client</li> <li>%b Size of the object returned, in bytes</li> </ul>
<pre>CustomLog /var/log/httpd/access_log common</pre>	Set up a log filename, with the format or (as in this case) the nickname specified
<pre>TransferLog /var/log/httpd/access_log</pre>	Set up a log filename, with format determined by the most recent <code>LogFormat</code> directive which did not define a nickname
<pre>TransferLog " rotatelog access_log 86400"</pre>	Organize log rotation every 24 hours
<pre>HostnameLookups Off</pre>	<p>Disable DNS hostname lookup to save network traffic. Hostnames can be resolved later by processing the log file:</p> <pre>logresolve &lt;access_log &gt;accessdns_log</pre>

httpd.conf	
Limited scope directives	
<pre>&lt;Directory "/var/www/html/foobar"&gt;   [list of directives] &lt;/Directory&gt;  &lt;Location /foobar&gt;   [list of directives] &lt;/Location&gt;</pre>	<p>Limit the scope of the specified directives to the directory <code>/var/www/html/foobar</code> and its subdirectories</p> <p>Limit the scope of the specified directive to the URL <code>http://www.mysite.org/foobar/</code> and its subdirectories</p>
Directory protection directives	
<pre>&lt;Directory "/var/www/html/protected"&gt;   AuthName "Protected zone"    AuthType Basic    AuthUserFile "/var/www/.htpasswd"    AuthGroupFile "/var/www/.htgroup"    Require valid-user    Allow from 10.13.13.0/24    Satisfy Any    Order Allow,Deny  &lt;/Directory&gt;</pre>	<p>Name of the realm. The client will be shown the realm name and prompted to enter an user and password</p> <p>Type of user authentication: <code>Basic</code>, <code>Digest</code>, <code>Form</code>, or <code>None</code></p> <p>User database file. Each line is in the format <code>user:encrypted_password</code> To add an user <code>jdoe</code> to the database file, use the command: <code>htpasswd -c /var/www/.htpasswd jdoe</code> (will prompt for his password)</p> <p>Group database file. Each line contains a groupname followed by all member usernames: <code>mygroup: jdoe ksmith mgreen</code></p> <p>Control who can access the protected resource.  <code>valid-user</code>      any user in the user database file  <code>user jdoe</code>        only the specified user  <code>group mygroup</code>    only the members of the specified group</p> <p>Control which host can access the protected resource</p> <p>Set the access policy concerning user and host control.  <code>All</code>      both <code>Require</code> and <code>Allow</code> criteria must be satisfied  <code>Any</code>      any of <code>Require</code> or <code>Allow</code> criteria must be satisfied</p> <p>Control the evaluation order of <code>Allow</code> and <code>Deny</code> directives.  <code>Allow,Deny</code>      First, all <code>Allow</code> directives are evaluated; at least one must match, or the request is rejected. Next, all <code>Deny</code> directives are evaluated; if any matches, the request is rejected. Last, any requests which do not match an <code>Allow</code> or a <code>Deny</code> directive are denied  <code>Deny,Allow</code>      First, all <code>Deny</code> directives are evaluated; if any match, the request is denied unless it also matches an <code>Allow</code> directive. Any requests which do not match any <code>Allow</code> or <code>Deny</code> directives are permitted</p>

httpd.conf	
SSL/TLS directives (module mod_ssl)	
SSLCertificateFile \ /etc/httpd/conf/ssl.crt/server.crt	SSL server certificate
SSLCertificateKeyFile \ /etc/httpd/conf/ssl.key/server.key	SSL server private key (for security reasons, this file should be readable only by root)
SSLCACertificatePath \ /usr/local/apache2/conf/ssl.crt/	Directory containing the certificates of CAs. Files in this directory are PEM-encoded and accessed via symlinks to hash filenames
SSLCACertificateFile \ /usr/local/apache2/conf/ssl.crt/ca-bundle.crt	Certificates of CAs. Certificates are PEM-encoded and concatenated in a single bundle file in order of preference
SSLCertificateChainFile \ /usr/local/apache2/conf/ssl.crt/ca.crt	Certificate chain of the CAs. Certificates are PEM-encoded and concatenated from the issuing CA certificate of the server certificate to the root CA certificate. Optional
SSLEngine on	Enable the SSL/TLS Protocol Engine
SSLProtocol +SSLv3 +TLSv1.2	SSL protocol flavors that the client can use to connect to server. Possible values are: SSLv2 (deprecated) SSLv3 TLSv1 TLSv1.1 TLSv1.2 All (all the above protocols)
SSLCipherSuite \ ALL:!aDH:RC4+RSA:+HIGH:+MEDIUM:+LOW:+SSLv2:+EXP	Cipher suite available for the SSL handshake (key exchange algorithms, authentication algorithms, cipher/encryption algorithms, MAC digest algorithms)
ServerTokens Full	Server response header field to send back to client. Possible values are: Prod sends Server: Apache Major sends Server: Apache/2 Minor sends Server: Apache/2.4 Minimal sends Server: Apache/2.4.2 OS sends Server: Apache/2.4.2 (Unix) Full (or not specified) sends Server: Apache/2.4.2 (Unix) PHP/4.2.2 MyMod/1.2
ServerSignature Off	Trailing footer line on server-generated documents. Possible values are: Off no footer line (default) On server version number and ServerName EMail as above, plus a mailto link to ServerAdmin
SSLVerifyClient none	Certificate verification level for client authentication. Possible values are: none no client certificate is required require the client needs to present a valid certificate optional the client may present a valid certificate (this option is unused as it doesn't work on all browsers) optional_no_ca the client may present a valid certificate but it doesn't need to be successfully verifiable (this option has not much purpose and is used only for SSL testing)
TraceEnable on	Enable TRACE requests

```
openssl x509 -text -in certif.crt -noout
openssl req -text -in request.csr -noout
openssl req -new -key private.key -out request.csr

openssl req -new -nodes -keyout private.key \
-out request.csr -newkey rsa:2048

openssl req -x509 -newkey rsa:2048 -nodes \
-keyout private.key -out certif.crt -days validity

openssl ca -config ca.conf -in request.csr \
-out certif.crt -days validity -verbose

openssl ca -config ca.conf -gencrl -revoke certif.crt \
-crl_reason why

openssl ca -config ca.conf -gencrl -out crlist.crl
```

```
openssl x509 -in certif.pem -outform DER \
-out certif.der

openssl pkcs12 -export -in certif.pem \
-inkey private.key -out certif.pfx -name friendlyname

cat cert.crt cert.key > cert.pem
```

```
openssl dgst -hashfunction -out file.hash file
openssl dgst -hashfunction file | cmp -b file.hash

openssl dgst -hashfunction -sign private.key \
-out file.sig file

openssl dgst -hashfunction -verify public.key \
-signature file.sig file

openssl enc -e -cipher -in file -out file.enc -salt
openssl enc -d -cipher -in file.enc -out file
```

```
openssl genpkey -algorithm RSA -cipher 3des \
-pkeyopt rsa_keygen_bits:2048 -out key.pem

openssl genrsa -des3 -out key.pem 2048

openssl pkey -text -in private.key -noout
openssl rsa -text -in private.key -noout

openssl pkey -in old.key -out new.key -cipher
openssl rsa -in old.key -out new.key -cipher

openssl pkey -in old.key -out new.key
```

1. `openssl s_client -connect www.website.com:443 > tmpfile`
2. **CTRL** **C**
3. `openssl x509 -in tmpfile -text`

```
openssl list-message-digest-commands
openssl list-cipher-commands
```

Read a certificate

Read a Certificate Signing Request

Generate a Certificate Signing Request (in PEM format) for the public key of a key pair

Create a 2048-bit RSA key pair and generate a Certificate Signing Request for it

Generate a new CA private key, create a 2048-bit RSA key pair and generate a CSR for it

Sign a CSR (to generate a self-signed certificate, the steps are creating a CSR and signing it)

Revoke a certificate

Generate a Certificate Revocation List containing all revoked certificates so far

Convert a certificate from PEM to DER

Convert a certificate from PEM to PKCS#12 including the private key

Create a PEM certificate from CRT and private key

Generate the digest of a file

Verify the digest of a file (if there is no output, then digest verification is successful)

Generate the signature of a file

Verify the signature of a file

Encrypt a file

Decrypt a file

Generate a 2048-bit RSA key pair protected by TripleDES passphrase

Generate a 2048-bit RSA key pair protected by TripleDES passphrase (older versions of OpenSSL)

Examine a private key

Examine a private key (older versions of OpenSSL)

Change the passphrase of a private key

Change the passphrase of a private key (older versions of OpenSSL)

Remove the passphrase from a private key

Retrieve and inspect a SSL certificate from a website

List all available hash functions

List all available ciphers

CA.pl -newca	Create a Certification Authority hierarchy
CA.pl -newreq	Generate a Certificate Signing Request
CA.pl -signreq	Sign a Certificate Signing Request
CA.pl -pkcs12 " <i>Certificate name</i> "	Generate a PKCS#12 certificate from a Certificate Signing Request
CA.pl -newcert	Generate a self-signed certificate
CA.pl -newreq-nodes	Generate a Certificate Signing Request, with unencrypted private key (this is necessary for use in servers, because the private key is accessed in non-interactive mode i.e. without passphrase typing)
CA.pl -verify	Verify a certificate against the Certification Authority certificate for "demoCA"



Samba is a cross-platform implementation of Microsoft's SMB (Server Message Block) protocol for file and printer sharing. SMB is sometimes also referred to as CIFS (Common Internet File System). WINS (Windows Internet Name Service) is a name service used to translate NetBIOS names to IP addresses.

Ports used:	TCP 137	name service requests and responses
	TCP 138	datagram services e.g. server announcements
	TCP 139	file and printer sharing
	UDP	registration and translation of NetBIOS names, network browsing

smbd	Server Message Block daemon. Provides SMB file and printer sharing, browser services, user authentication, and resource lock. An extra copy of this daemon runs for each client connected to the server
nmbd	NetBIOS Name Service daemon. Handles NetBIOS name lookups, WINS requests, list browsing and elections. An extra copy of this daemon runs if Samba functions as a WINS server. Another extra copy of this daemon runs if DNS is used to translate NetBIOS names

/etc/smb/lmhosts	Samba NetBIOS hosts file
/etc/smb/netlogon	User logon directory

mount.cifs //smbserver/share1 /mnt/shares/sh1 \	Mount a Samba share on a Linux filesystem, using the CIFS filesystem interface. Access is checked upon a credentials file /etc/smbcreds (should be readable only by root) formatted as follows:
-o auto,credentials=/etc/smbcreds	
	username = jdoe
	password = jd03s3cr3t

smbmount //smbserver/share1 /mnt/shares/sh1 \	Mount a Samba share as user jdoe
-o username=jdoe	

smbstatus	Display current information about shares, clients connections, and locked files
-----------	---

smbclient //smbserver/share1	Access a Samba share on a server (with a FTP-like interface)
------------------------------	--

smbclient -L //smbserver -W WORKGROUP -U user	List the Samba resources available on a server, belonging to the specified workgroup and accessible to the specified user
---	---

cat msg.txt   smbclient -M client -U user	Show a message popup on the client machine (using the WinPopup protocol)
---	--

smbpasswd jdoe	Change the Samba password of the specified user
----------------	---

smbpasswd -a ksmith	Create a new Samba user and set his password
---------------------	--

nmblookup smbserver	Look up the NetBIOS name of a server and map it to an IP address
---------------------	--

nmblookup -U winsserver -R WORKGROUP#1B	Query recursively a WINS server for the Domain Master Browser for the specified workgroup
---	---

nmblookup -U winsserver -R WORKGROUP#1D	Query recursively a WINS server for the Domain Controller for the specified workgroup
---	---

testparm	Check for errors in the Samba configuration file
----------	--

net	Tool for administration of Samba and remote CIFS servers
-----	--

net rpc shutdown -r -S smbserver -U root%password	Reboot a CIFS server
---	----------------------

net rpc service list -S smbserver	List available service on a CIFS server
-----------------------------------	---

net status sessions	Show active Samba sessions
---------------------	----------------------------

net status shares	Show Samba shares
-------------------	-------------------

net rpc info	Show information about the domain
--------------	-----------------------------------

net groupmap list	Show group mappings between Samba and Windows
-------------------	---

<code>/etc/smb/smb.conf</code>	Samba configuration
<pre>[global]  workgroup = MYWORKGROUP  server string = Linux Samba Server %L  hosts allow = 10.9.9.0/255.255.255.0  security = user  encrypt passwords = yes  smb passwd file = /etc/smb/smbpasswd  unix password sync = yes  username map = /etc/smb/smbusers  netbios name = Mysambabox netbios aliases = Mysambabox1  wins support = yes  logon server = yes  log file = /var/log/samba/log.%m max log size = 1000 syslog only = no syslog = 0  panic action = \ /usr/share/samba/panic-action %d</pre>	<p>Global server settings: defines parameters applicable for the whole Samba server and sets the defaults that will be used for the parameters not mentioned in other sections</p> <p>Make Samba join the specified workgroup</p> <p>Describe server to the clients</p> <p>Allow only the specified machines to connect to the server</p> <p>Set up user-level authentication</p> <p>Use encrypted passwords</p> <p>Refer to the specified password file for user authentication. A new user's password will need to be set both in Linux and Samba by using these commands from shell prompt:  <code>passwd newuser</code>  <code>smbpasswd newuser</code></p> <p>When the password of a client user (e.g. under Windows) is changed, change the Linux and Samba password too</p> <p>Map each Samba server user name to client user name(s). The file <code>/etc/smb/smbusers</code> is structured as follows:  <code>root = Administrator Admin</code>  <code>jdoe = "John Doe"</code>  <code>kgreen = "Kim Green"</code></p> <p>Set NetBIOS name and alias</p> <p>Make Samba play the role of a WINS server.  Note: There should be only one WINS server on a network</p> <p>Enable logon support.  Logon script parameters will be defined in a <code>[netlogon]</code> section</p> <p>Use a separate logfile for each machine that connects</p> <p>Maximum size of each logfile, in Kb</p> <p>Whether to log only via Syslog</p> <p>Log everything to the logfiles <code>/var/log/smb/log.smbd</code> and <code>/var/log/smb/log.nmbd</code>, and log a minimum amount of information to Syslog. This parameter can be set to a higher value to have Syslog log more information</p> <p>Mail a backtrace to the sysadmin in case Samba crashes</p>
<pre>[netlogon] comment = Netlogon for Windows clients path = /home/netlogon browseable = no guest ok = no writeable = no logon script = %U.bat</pre>	<p>Section defining a logon script.  Specifies a per-user script e.g. <code>/home/netlogon/jdoe.bat</code> will be called when user <code>jdoe</code> logs in. It is also possible to specify a per-clientname script <code>%m.bat</code>, which will be called when a specific machine logs in.  Guest access to the service (i.e. access without entering a password) is disabled</p>
<pre>[Canon LaserJet 3] printer name = lp comment = Canon LaserJet 3 main printer path = /var/spool/lpd/samba printable = yes writeable = no</pre>	<p>Section defining a printer accessible via the network</p>

<code>/etc/smb/smb.conf</code> Samba configuration	
<pre>[public] comment = Public Storage on %L path = /home/samba browsable = yes writeable = yes</pre>	<p>Section defining a public share accessible on read/write by anyone</p> <p>Describe the public share to users</p> <p>Path of the public share on the server</p> <p>Whether to show the public share when browsing</p> <p>Whether to allow all users to write in this directory</p>
<pre>[homes]  comment = %U's home directory on %L from %m browseable = no writeable = yes</pre>	<p>Section enabling users that have an account and a home directory on the Samba server to access it and modify its contents from a Samba client. The <code>path</code> variable is not set, by default is <code>path=/home/%S</code></p> <p>Describe the share to the user</p> <p>Whether to show the homes share when browsing</p> <p>Whether to allow the user to write in his home directory</p>
<pre>[foobar] path = /foobar comment = Share Foobar on %L from %m browsable = yes writeable = yes  valid users = jdoe, kgreen, +geeks invalid users = csmith read list = bcameron write list = fcastle</pre>	<p>Section defining a specific share</p> <p>Allow access only to users jdoe and kgreen, and local group geeks</p> <p>Deny access to user csmith</p> <p>Allow read-only access to user bcameron</p> <p>Allow read-write access to user fcastle</p>

Samba share access	
User-level authentication	
<pre>[global] security = user guest account = nobody map to guest = Never</pre>	<p>Set up user-level authentication</p> <p>Map the guest account to the system user nobody (default)</p> <p>Specify how incoming requests are mapped to the guest account:</p> <p>Bad User        redirect from an invalid user to guest account on server</p> <p>Bad Password    redirect from an invalid password to guest account on server</p> <p>Never            reject unauthenticated users</p>
Server-level authentication	
<pre>[global] security = server password server = srv1 srv2</pre>	<p>Set up server-level authentication</p> <p>Authenticate to server srv1, or to server srv2 if srv1 is unavailable</p>
Domain-level authentication	
<pre>[global] security = ADS realm = KRB_REALM</pre>	<p>Set up domain-level authentication as an Active Directory member server</p> <p>Join the specified realm.</p> <p>Kerberos must be installed and an administrator account must be created:</p> <pre>net ads join -U Administrator%password</pre>
Share-level authentication	
<pre>[global] security = share  [foobar] path = /foobar username = foobaruser only user = yes</pre>	<p>Set up share-level authentication</p> <p>Define a share accessible to any user which can supply foobaruser's password.</p> <p>The user foobaruser must be created on the system:</p> <pre>useradd -c "Foobar account" -d /tmp -m -s /sbin/nologin foobaruser</pre> <p>and added to the Samba password file:</p> <pre>smbpasswd -a foobaruser</pre>

Samba macros			
%S	Username	The substitutes below apply only to the configuration options that are used when a connection has been established:	
%U	Session username (the username that the client requested, not necessarily the same as the one he got)		
%G	Primary group of session username	%S	Name of the current service, if any
%h	Samba server hostname	%P	Root directory of the current service, if any
%M	Client hostname	%u	Username of the current service, if any
%L	NetBIOS name of the server	%g	Primary group name of username
%m	NetBIOS name of the client	%H	Home directory of username
%d	Process ID of the current server process	%N	Name of the NIS home directory server as obtained from the NIS <code>auto.map</code> entry. Same as %L if Samba was not compiled with the <code>--with-automount</code> option
%a	Architecture of remote machine	%p	Path of service's home directory as obtained from the NIS <code>auto.map</code> entry. The NIS <code>auto.map</code> entry is split up as %N:%p
%I	IP address of client machine		
%i	Local IP address to which a client connected		
%T	Current date and time		
%D	Domain or workgroup of the current user		
%w	Winbind separator		
%(var)	Value of the environment variable <i>var</i>		

A Network File System (NFS) server makes filesystems available to clients for mounting.

The portmapper is needed by NFS to map incoming TCP/IP connections to the appropriate NFS RPC calls. Some Linux distributions use rpcbind instead of the portmapper.

For security, the TCP Wrapper should be configured to limit access to the portmapper to NFS clients only:

file `/etc/hosts.deny` should contain `portmap: ALL`

file `/etc/hosts.allow` should contain `portmap: IP_addresses_of_clients`

NFS handles user permissions across systems by considering users with same UID and username as the same user.

Group permission is evaluated similarly, by GID and groupname.

`rpc.nfsd`  
`rpc.mountd`  
`rpc.lockd`  
`rpc.statd`

NFS daemons

`/etc/exports`

List of the filesystems to be exported (via the command `exportfs`)

`/var/lib/nfs/xtab`

List of exported filesystems, maintained by `exportfs`

`/proc/fs/nfs/exports`

Kernel export table (can be examined via the command `cat`)

`exportfs -ra`

Export or reexport all directories.

When exporting, fills the kernel export table `/proc/fs/nfs/exports`.

When reexporting, removes those entries in `/var/lib/nfs/xtab` that are deleted from `/etc/exports` (therefore synchronizing the two files), and removes those entries from `/proc/fs/nfs/exports` that are no longer valid

`exportfs -ua`

Unexport all directories.

Removes from `/proc/fs/nfs/exports` all those entries that are listed in `/var/lib/nfs/xtab`, and clears the latter file

`showmount`

Show the remote client hosts currently having active mounts

`showmount --directories`

Show the directories currently mounted by a remote client host

`showmount --exports`

Show the filesystems currently exported i.e. the active export list

`showmount --all`

Show both remote client hosts and directories

`showmount -e nfsserver`

Show the shares a NFS server has available for mounting

`mount -t nfs nfsserver:/share /usr`

Command to be run on a client to mount locally a remote NFS share.

NFS shares accessed frequently should be added to `/etc/fstab`:

`nfsserver:/share /usr nfs intr 0 0`

`rpcinfo -p nfsserver`

Probe the portmapper on a NFS server and display the list of all registered RPC services there

`rpcinfo -t nfsserver nfs`

Test a NFS connection by sending a null pseudo request (using TCP)

`rpcinfo -u nfsserver nfs`

Test a NFS connection by sending a null pseudo request (using UDP)

`nfsstat`

Display NFS/RPC client/server statistics.

Options:

	NFS	RPC	both
server	-sn	-sr	-s
client	-cn	-cr	-c
both	-n	-r	-nr

/etc/exports	
/export/	10.3.3.3(rw)
/export/	*(ro, sync)
/home/ftp/pub	client1(rw) *.example.org(ro)
/home/crew	@FOOBARWORKGROUP(rw) (ro)

<b>filesystem</b>	Filesystem on the NFS server to be exported to clients	
<b>client identity</b>	Client systems allowed to access the exported directory. Can be identified by hostname, IP address, wildcard, subnet, or @NIS workgroup. Multiple client systems can be listed, and each one can have different options	
<b>client options</b>	ro	Read-only access (default)
	rw	Read and write access. The client may choose to mount read-only anyway
	sync	Reply to requests only after the changes made by these requests have been committed to stable storage
	async	Reply to requests without waiting that changes are committed to stable storage. Improves performances but might cause loss or corruption of data if server crashes
	root_squash	Requests by user <code>root</code> on client will be done as user <code>nobody</code> on server (default)
	no_root_squash	Requests by user <code>root</code> on client will be done as same user <code>root</code> on server
	all_squash	Requests by a non-root user on client will be done as user <code>nobody</code> on server
	no_all_squash	Requests by a non-root user on client will be attempted as same user on server (default)

A DHCP (Dynamic Host Configuration Protocol) server listens for requests on UDP port 67 and answers to UDP port 68. The assignment of an IP address to a host is done through a sequence of DHCP messages initiated by the client host: DHCP Discover, DHCP Offer, DHCP Request, DHCP Acknowledgment. Because DHCP Discover messages are broadcast and therefore not routed outside a LAN, a DHCP relay agent is necessary for those clients situated outside the DHCP server's LAN. The DHCP relay agent listens to DHCP Discover messages and relays them in unicast to the DHCP server.

<code>/etc/dhcpd.conf</code>	Configuration file for the DHCP server
<code>/etc/sysconfig/dhcrelay</code> (SUSE)	Configuration file for the DHCP relay agent
<code>/var/lib/dhcpd/dhcpd.leases</code>	DHCP current leases

<code>/etc/dhcpd.conf</code>	
<pre>option domain-name-servers 10.2.2.2; option smtp-servers 10.3.3.3; option pop-servers 10.4.4.4; option time-servers 10.5.5.5; option nntp-servers 10.6.6.6;</pre>	Global parameters for DNS, mail, NTP, and news servers specification
<pre>shared-network geek-net {     default-lease-time 86400;      max-lease-time 172800;      option routers 10.0.3.252;     option broadcast-address 10.0.3.255;      subnet 10.0.3.0 netmask 255.255.255.128 {         range 10.0.3.1 10.0.3.101;     }     subnet 10.0.3.128 netmask 255.255.255.128 {         range 10.0.3.129 10.0.3.229;     } }</pre>	<p>Definition of a network</p> <p>Time, in seconds, that will be assigned to a lease if a client does not ask for a specific expiration time</p> <p>Maximum time, in seconds, that can be assigned to a lease if a client asks for a specific expiration time</p> <p>Definition of different subnets in the network, with specification of different ranges of IP addresses that will be leased to clients depending on the client's subnet</p>
<pre>group {     option routers 10.0.17.252;     option broadcast-address 10.0.17.255;     netmask 255.255.255.0;     host linuxbox1 {         hardware ethernet AA:BB:CC:DD:EE:FF;         fixed-address 10.0.17.42;         option host-name "linuxbox1";     }     host linuxbox2 {         hardware ethernet 33:44:55:66:77:88;         fixed-address 10.0.17.66;         option host-name "linuxbox2";     } }</pre>	<p>Definition of a group</p> <p>Definition of different hosts to whom static IP addresses will be assigned to, depending on their MAC address</p>

PAM (Pluggable Authentication Modules) is an abstraction layer that allows applications to use authentication methods while being implementation-agnostic.

```
/etc/pam.d/service          PAM configuration for service
/etc/pam.conf (obsolete)    PAM configuration for all services

ldd /usr/sbin/service | grep libpam    Check if service is enabled to use PAM
```

/etc/pam.d/service		
auth	requisite	pam_securetty.so
auth	required	pam_nologin.so
auth	required	pam_env.so
auth	required	pam_unix.so nullok
account	required	pam_unix.so
session	required	pam_unix.so
session	optional	pam_lastlog.so
password	required	pam_unix.so nullok obscure min=4 max=8

<b>type</b>	auth	Authentication module to verify user identity and group membership
	account	Authorization module to determine user's right to access a resource (other than his identity)
	password	Module to update an user's authentication credentials
	session	Module (run at end and beginning of an user session) to set up the user environment
<b>control</b>	optional	Module is not critical to the success or failure of <i>service</i>
	sufficient	If this module succeeds, and no previous module has failed, module stack processing ends successfully. If this module fails, it is non-fatal and processing of the stack continues
	required	If this module fails, processing of the stack continues until the end, and <i>service</i> fails
	requisite	If this module fails, <i>service</i> fails and control returns to the application that invoked <i>service</i>
	include	Include modules from another PAM service file
<b>module</b>	PAM module and its options, e.g.:	
	pam_unix.so	Standard UNIX authentication module via <i>/etc/passwd</i> and <i>/etc/shadow</i>
	pam_nis.so	Module for authentication via NIS
	pam_ldap.so	Module for authentication via LDAP
	pam_fshadow.so	Module for authentication against an alternative shadow passwords file
	pam_cracklib.so	Module for password strength policies (e.g. length, case, max n of retries)
	pam_limits.so	Module for system policies and system resource usage limits
	pam_listfile.so	Module to deny or allow the service based on an arbitrary text file



LDAP (Lightweight Directory Access Protocol) is a simplified version of the X.500 standard and uses TCP port 389. LDAP permits to organize hierarchically a database of entries, each one of which is identified by a unique DN (Distinguished Name). Each DN has a set of attributes, each one of which has a value. An attribute may appear multiple times.

Most frequently used LDAP attributes		
Attribute	Example	Meaning
dn	dn: cn=John Doe,dc=example,dc=org	Distinguished Name (not an attribute; identifies the entry)
dc	dc=example,dc=org	Domain Component
cn	cn: John Doe	Common Name
givenName	givenName: John	Firstname
sn	sn: Doe	Surname
mail	mail: jdoe@example.org	Email address
telephoneNumber	telephoneNumber: +1 505 1234 567	Telephone number
uid	uid: jdoe	User ID
c	c: US	Country code
l	l: San Francisco	Locality
st	st: California	State or province
street	street: 42, Penguin road	Street
o	o: Example Corporation	Organization
ou	ou: IT Dept	Organizational Unit
manager	manager: cn=Kim Green,dc=example,dc=org	Manager

```
ldapsearch -H ldap://ldapserver.example.org \
-s base -b "ou=people,dc=example,dc=com" \
"(sn=Doe)" cn sn telephoneNumber
```

Query the specified LDAP server for entries where surname=Doe, and print common name, surname, and telephone number of the resulting entries. Output is shown in LDIF

```
ldappasswd -x -D "cn=Admin,dc=example,dc=org" \
-W -S "uid=jdoe,ou=IT Dept,dc=example,dc=org"
```

Authenticating as Admin, change the password of user jdoe in the OU called IT Dept, on example.org

```
ldapmodify -b -r -f /tmp/mods.ldif
```

Modify an entry according to the LDIF file /tmp/mods.ldif

```
ldapadd -h ldapserver.example.org \
-D "cn=Admin" -W -f /tmp/mods.ldif
```

Authenticating as Admin, add an entry by adding the content of the LDIF file /tmp/mods.ldif to the directory. Actually invokes the command `ldapmodify -a`

```
ldapdelete -v "uid=jdoe,dc=example,dc=org" \
-D "cn=Admin,dc=example,dc=org" -W
```

Authenticating as Admin, delete the entry of user jdoe

LDIF (LDAP Data Interchange Format)	
dn: cn=John Doe, dc=example, dc=org changetype: modify replace: mail mail: johndoe@othercorp.org - add: jpegPhoto jpegPhoto:< file://tmp/jdoe.jpg - delete: description -	This LDIF file will change the email address of jdoe, add a picture, and delete the description attribute for the entry

<code>slapd</code>	Standalone OpenLDAP daemon
<code>/var/lib/ldap/</code>	Files constituting the OpenLDAP database
<code>/etc/openldap/slapd.conf</code> <code>/usr/local/etc/openldap/slapd.conf</code>	OpenLDAP configuration file
<code>slapcat -l file.ldif</code>	Dump the contents of an OpenLDAP database to a LDIF file
<code>slapadd -l file.ldif</code>	Import an OpenLDAP database from a LDIF file
<code>slapindex</code>	Regenerate OpenLDAP's database indexes

SSSD (the System Security Services Daemon) can be used to provide access to OpenLDAP as an authentication and identity provider.

Security-Enhanced Linux (SELinux) is a Linux kernel security module that provides a mechanism for supporting access control security policies.

	Debian	Red Hat
Enter permissive mode	<code>echo 0 &gt; /selinux/enforce</code>	<code>setenforce 0</code>
Enter enforcing mode	<code>echo 1 &gt; /selinux/enforce</code>	<code>setenforce 1</code>
Display mode	<code>cat /selinux/enforce</code>	<code>getenforce</code>
Set mode permanently		<p>Mode can be configured permanently in <code>/etc/selinux/config</code> (symlinked in <code>/etc/sysconfig/selinux</code>)</p> <pre># This file controls the state of SELinux on the system. # SELINUX= can take one of these three values: # enforcing - SELinux security policy is enforced. # permissive - SELinux prints warnings instead of enforcing. # disabled - No SELinux policy is loaded. SELINUX=enforcing # SELINUXTYPE= can take one of these two values: # targeted - Only targeted network daemons are protected. # strict - Full SELinux protection. SELINUXTYPE=targeted</pre>

Tag		Attributes	
<b>&lt;h1&gt;...&lt;h6&gt; Heading</b>		<code>align=left center right justify</code>	Heading alignment †
<b>&lt;br&gt; Line break</b>	Line break and carriage return		
<b>&lt;hr&gt; Horizontal line</b>		<code>align=left center right</code> <code>noshade</code> <code>size=npixels</code> <code>width=npixels percent%</code>	Line alignment † Solid rendering instead of 3D † Line height Line width
<b>&lt;p&gt; Paragraph</b> <b>&lt;div&gt; Section</b>		<code>align=left center right justify</code>	Paragraph or section alignment †
<b>&lt;span&gt; Group</b>	Group of elements		
<b>&lt;a&gt; Anchor</b>	Hyperlink	<code>charset=encoding</code> <code>coords=left,top,right,bottom cx,cy,radius x1,y1,...,xn,yn</code> <code>href=url</code> <code>hreflang=language</code> <code>name=section</code> <code>rel rev=alternate stylesheet start next prev contents index glossary copyright chapter section subsection appendix help bookmark</code> <code>shape=rectangle circle polygon</code> <code>target=_blank _parent _self _top</code> <code>type=mimetype</code>	Character encoding of target URL Coordinates of region; depends on shape Target URL for the link Language of document at the target URL Name of anchor for document bookmarking Relationship between this document and the target URL ( <i>rel</i> ) or vice versa ( <i>rev</i> ) Shape of region Destination of target URL MIME type of target URL
<b>&lt;dl&gt; Definition list</b>			
<b>&lt;dt&gt; Definition term</b>			
<b>&lt;dd&gt; Definition description</b>	Description of a definition term		

† = deprecated

Tag		Attributes	
<b>&lt;i&gt; Italic</b>			
<b>&lt;b&gt; Bold</b>			
<b>&lt;s&gt; Strike-through</b>	Strike-through text †		
<b>&lt;u&gt; Underlined</b>	Underlined text †		
<b>&lt;big&gt; Bigger</b>			
<b>&lt;small&gt; Smaller</b>			
<b>&lt;sub&gt; Subscript</b>			
<b>&lt;sup&gt; Superscript</b>			
<b>&lt;tt&gt; Teletype</b>	Monospaced text		
<b>&lt;em&gt; Emphasized</b>			
<b>&lt;strong&gt; Strong</b>			
<b>&lt;del&gt; Deleted</b>	Deleted/inserted text	<code>cite=url</code>	URL to document explaining deletion/insertion
<b>&lt;ins&gt; Inserted</b>		<code>datetime=yyyy-mm-dd</code>	When the text was deleted/inserted
<b>&lt;pre&gt; Preformatted</b>		<code>width=ncharacters</code>	Max number of characters per line †
<b>&lt;code&gt; Code</b>	Source code text		
<b>&lt;samp&gt; Sample</b>	Sample code text		
<b>&lt;kbd&gt; Keyboard</b>	Keyboard key		
<b>&lt;var&gt; Variable</b>	Variable name		
<b>&lt;cite&gt; Citation</b>	Citation block		
<b>&lt;blockquote&gt; Quotation</b>		<code>cite=url</code>	URL to document containing the quote
<b>&lt;q&gt; Short quotation</b>			
<b>&lt;address&gt; Address</b>	Address block		
<b>&lt;abbr&gt; Abbreviation</b>			
<b>&lt;acronym&gt; Acronym</b>			
<b>&lt;dfn&gt; Definition</b>	Definition term		
<b>&lt;font&gt; Font</b>	Font †	<code>color=rgb(r,g,b)   #rrggbb   color</code>	Text color
		<code>face=fontname</code>	Text font
		<code>size=[1...7]   [-6...+6]</code>	Text size
<b>&lt;bdo&gt; Bidirectional override</b>		<code>dir=ltr rtl</code>	Direction of text: left-to-right or right-to-left
<b>&lt;xmp&gt; XMP</b>	Non-formatted text † ; ignores other HTML tags		
<b>other tags</b>	Attributes common to almost all other tags	<code>class=class style</code>	Class of the element
		<code>id=id</code>	Unique ID of the element
		<code>style=styledef</code>	Inline style definition
		<code>title=tooltip</code>	Text of the tooltip to display
		<code>dir=ltr rtl</code>	Direction of text: left-to-right or right-to-left
		<code>lang=language</code>	Language of the content
		<code>accesskey=character</code>	Keyboard shortcut for the element
		<code>tabindex=ntab</code>	N of tab for the element

† = deprecated

Tag	Attributes	
<b>&lt;img&gt; Image</b>	align=top bottom left middle right alt=alternatetext border=npixels height=npixels percent% hspace=npixels ismap=url longdesc=url src=url usemap=url vspace=npixels width=npixels percent%	Image alignment with respect to surrounding text † Description of the image for text-only browsers Border width around the image † Image height Blank space on the left and right side of image † URL for server-side image map URL containing a long description of the image URL of the image URL for client-side image map Blank space on top and bottom of image † Image width
<b>&lt;map&gt; Image map</b>	id=id name=name	Unique ID for the map tag Unique name for the map tag
<b>&lt;area&gt; Area of image map</b>	alt=alternatetext coords=left,top,right,bottom  cx,cy,radius x1,y1,...,xn,yn href=url nohref=true false shape=rectangle circle polygon target=_blank _parent _self _top	Description of area for text-only browsers Coordinates of clickable area; depends on shape Target URL of area Excludes or includes the area from image map Shape of area Destination of target URL

† = deprecated

Tag	Attributes	
<b>&lt;table&gt;</b> <b>Table</b>	align=left center right bgcolor=rgb( <i>r,g,b</i> ) #rrggbb color border=npixels cellpadding=npixels percent% cellspacing=npixels percent% frame=void above below lhs rhs hsides vsides box border rules=none groups rows cols all summary=summary width=npixels percent%	Table alignment † Table background color † Border width Space around the content of each cell Space between cells Visibility of sides of the table border Horizontal or vertical divider lines Summary of the table for text-only browsers Table width
<b>&lt;tr&gt;</b> <b>Table row</b>	align=left center right justify char bgcolor=rgb( <i>r,g,b</i> ) #rrggbb color char=character charoff=npixels percent% valign=top middle bottom baseline	Horizontal text alignment Row background color † Character to align text on, if align=char Alignment offset to first character, if align=char Vertical text alignment
<b>&lt;td&gt;</b> <b>Table cell</b> <b>&lt;th&gt;</b> <b>Table header</b>	abbr=content align=left center right justify char axis=category bgcolor=rgb( <i>r,g,b</i> ) #rrggbb color char=character charoff=npixels percent% colspan=ncolumns headers=headerid height=npixels nowrap rowspan=nrows scope=col colgroup row rowgroup valign=top middle bottom baseline width=npixels percent%	Abbreviated content in a cell Horizontal text alignment Cell name Cell background color † Character to align text on, if align=char Alignment offset to first character, if align=char Number of columns this cell spans on Cell header information for text-only browsers Cell height † Text in cell stays on a single line † Number of rows this cell spans on Target for cell header information Vertical text alignment Cell width †
<b>&lt;ol&gt;</b> <b>Ordered list</b>	compact=compact start=firstnumber type=A a I i 1	List must be more compact † Number to start the list on † List numbers type †
<b>&lt;ul&gt;</b> <b>Unordered list</b>	compact=compact type=disc square circle	List must be more compact † List type †
<b>&lt;li&gt;</b> <b>List item</b>	type=disc square circle A a I i 1 value=itemno	List item type † List item value †

† = deprecated

Dec	Hex	Char		Dec	Hex	Char		Dec	Hex	Char		Dec	Hex	Char	
0	0	<b>NUL</b>	Null	32	20	<b>space</b>		64	40	<b>@</b>		96	60	<b>`</b>	
1	1	<b>SOH</b>	Start of heading	33	21	<b>!</b>		65	41	<b>A</b>		97	61	<b>a</b>	
2	2	<b>STX</b>	Start of text	34	22	<b>"</b>		66	42	<b>B</b>		98	62	<b>b</b>	
3	3	<b>ETX</b>	End of text	35	23	<b>#</b>		67	43	<b>C</b>		99	63	<b>c</b>	
4	4	<b>EOT</b>	End of transmission	36	24	<b>\$</b>		68	44	<b>D</b>		100	64	<b>d</b>	
5	5	<b>ENQ</b>	Enquiry	37	25	<b>%</b>		69	45	<b>E</b>		101	65	<b>e</b>	
6	6	<b>ACK</b>	Acknowledge	38	26	<b>&amp;</b>		70	46	<b>F</b>		102	66	<b>f</b>	
7	7	<b>BEL</b>	Bell	39	27	<b>'</b>		71	47	<b>G</b>		103	67	<b>g</b>	
8	8	<b>BS</b>	Backspace	40	28	<b>(</b>		72	48	<b>H</b>		104	68	<b>h</b>	
9	9	<b>TAB</b>	Horizontal tab	41	29	<b>)</b>		73	49	<b>I</b>		105	69	<b>i</b>	
10	A	<b>LF</b>	Line feed	42	2A	<b>*</b>		74	4A	<b>J</b>		106	6A	<b>j</b>	
11	B	<b>VT</b>	Vertical tab	43	2B	<b>+</b>		75	4B	<b>K</b>		107	6B	<b>k</b>	
12	C	<b>FF</b>	Form feed	44	2C	<b>,</b>		76	4C	<b>L</b>		108	6C	<b>l</b>	
13	D	<b>CR</b>	Carriage return	45	2D	<b>-</b>		77	4D	<b>M</b>		109	6D	<b>m</b>	
14	E	<b>SO</b>	Shift out	46	2E	<b>.</b>		78	4E	<b>N</b>		110	6E	<b>n</b>	
15	F	<b>SI</b>	Shift in	47	2F	<b>/</b>		79	4F	<b>O</b>		111	6F	<b>o</b>	
16	10	<b>DLE</b>	Data link escape	48	30	<b>0</b>		80	50	<b>P</b>		112	70	<b>p</b>	
17	11	<b>DC1</b>	Device control 1	49	31	<b>1</b>		81	51	<b>Q</b>		113	71	<b>q</b>	
18	12	<b>DC2</b>	Device control 2	50	32	<b>2</b>		82	52	<b>R</b>		114	72	<b>r</b>	
19	13	<b>DC3</b>	Device control 3	51	33	<b>3</b>		83	53	<b>S</b>		115	73	<b>s</b>	
20	14	<b>DC4</b>	Device control 4	52	34	<b>4</b>		84	54	<b>T</b>		116	74	<b>t</b>	
21	15	<b>NAK</b>	Negative ACK	53	35	<b>5</b>		85	55	<b>U</b>		117	75	<b>u</b>	
22	16	<b>SYN</b>	Synchronous idle	54	36	<b>6</b>		86	56	<b>V</b>		118	76	<b>v</b>	
23	17	<b>ETB</b>	End of Tx block	55	37	<b>7</b>		87	57	<b>W</b>		119	77	<b>w</b>	
24	18	<b>CAN</b>	Cancel	56	38	<b>8</b>		88	58	<b>X</b>		120	78	<b>x</b>	
25	19	<b>EM</b>	End of medium	57	39	<b>9</b>		89	59	<b>Y</b>		121	79	<b>y</b>	
26	1A	<b>SUB</b>	Substitute	58	3A	<b>:</b>		90	5A	<b>Z</b>		122	7A	<b>z</b>	
27	1B	<b>ESC</b>	Escape	59	3B	<b>;</b>		91	5B	<b>[</b>		123	7B	<b>{</b>	
28	1C	<b>FS</b>	File separator	60	3C	<b>&lt;</b>		92	5C	<b>\</b>		124	7C	<b> </b>	
29	1D	<b>GS</b>	Group separator	61	3D	<b>=</b>		93	5D	<b>]</b>		125	7D	<b>}</b>	
30	1E	<b>RS</b>	Record separator	62	3E	<b>&gt;</b>		94	5E	<b>^</b>		126	7E	<b>~</b>	
31	1F	<b>US</b>	Unit separator	63	3F	<b>?</b>		95	5F	<b>_</b>		127	7F	<b>DEL</b>	Delete

Characters 0-31 and 127 are non-printable.